

CodroidCS SDK Manual

Version: 2.1.7 | Namespace: Codroid

Table of Contents

- [1. Quick Start](#)
- [2. Core Concepts](#)
- [3. CodroidClient API Reference](#)
- [4. Motion API Reference](#)
- [5. Data Types and Enums](#)
- [6. CRI Real-Time Data and Control API Reference](#)
- [7. IO and Register API Reference](#)
- [8. Utilities API Reference](#)
- [9. .NET Framework 4.6.2 Notes](#)

Environment Requirements

Target	Platform	Notes
net6.0	Linux, Windows, macOS	.NET 6 SDK
net8.0	Linux, Windows, macOS	.NET 8 SDK (recommended)
net462	Windows only	.NET Framework 4.6.2+, WinForms/WPF compatible

Install via NuGet

```
dotnet add package Codroidsdk
```

Project Reference

```
dotnet add path/to/YourApp.csproj reference path/to/CodroidSDK/CodroidCS.csproj
```

API Naming Convention

All public methods return `Task` / `Task<T>` but do **not** use the `Async` suffix.

```
// Correct
await robot.ConnectRemoteAndSwitchOn();
int di = await robot.GetDi(0);

// Wrong
await robot.ConnectRemoteAndSwitchOnAsync(); // does not exist
```

This keeps the same public API names across C#, Python, and C++ SDKs.

Unit Convention

Layer	Linear	Angular
SDK public API	mm	deg (degrees)
TCP JSON protocol	mm	deg
CRI UDP binary (wire)	m	rad (radians)
<code>CriRealTimeData</code> (parsed)	mm	deg

`CriRealtimePacketParser.Parse()` and `CriRealtimeDispatcher` (with `convertToSi=true`) handle the m-to-mm and rad-to-deg conversion automatically.

1. Quick Start

Install

NuGet

```
dotnet add package Codroidsdk
```

Project Reference

```
dotnet add path/to/YourApp.csproj reference path/to/CodroidSDK/CodroidCS.csproj
```

Supported Targets

```
<!-- net8.0 (recommended) -->
<TargetFramework>net8.0</TargetFramework>

<!-- net6.0 -->
<TargetFramework>net6.0</TargetFramework>

<!-- .NET Framework 4.6.2+ (Windows only) -->
<TargetFramework>net462</TargetFramework>
```

Minimal Example

Connect to the controller, read a digital input, write a digital output, and disconnect.

```
using Codroid;

var robot = new CodroidClient("192.168.8.136");

try
```

```

{
    // Connect, enter remote mode, and power on
    await robot.ConnectRemoteAndSwitchOn();
    // ⚠️ Start CRI data push (required for sync motion)
    await robot.StartCriDataPush("192.168.8.150", 18888);
    await robot.WaitForCriData(5.0); // Start CRI data push (required for sync
motion)

    // Read DI port 0
    int di0 = await robot.GetDi(0);
    Console.WriteLine($"DI 0 = {di0}");

    // Write DI value to DO port 10
    await robot.SetDo(10, di0);
}
finally
{
    // Always disconnect in finally
    robot.Disconnect();
}

```

Complete Workflow Example

```

using Codroid;

ConsoleUtf8.InitConsoleUtf8(); // Windows console UTF-8

var robot = new CodroidClient("192.168.8.136");

try
{
    // 1. Connect
    await robot.ConnectRemoteAndSwitchOn();
    // ⚠️ Start CRI data push (required for sync motion)
    await robot.StartCriDataPush("192.168.8.150", 18888);

```

```
    await robot.WaitForCriData(5.0); // Start CRI data push (required for sync
motion)

// 2. IO
int di0 = await robot.GetDi(0);
await robot.SetDo(10, di0);

// 3. Register
RegisterReadValue reg = await robot.GetRegisterValue(49100);
int value = reg.GetInt32();
await robot.SetRegisterValue(49100, value + 1);

// 4. Motion
await robot.MovJ(JointPoint.Degrees(new[] { 0, 0, 90, 0, 90, 0 }), speed: 40, acc:
100);

// 5. Blocking motion
robot.MovLSync(
    CartesianPoint.MmDegWithRef(new[] { 400, 0, 300, 180, 0, 0 },
robot.CriData.JointPosition),
    speed: 150, acc: 500);
}
finally
{
    robot.Disconnect();
}
```

Run Example Projects

```
# net8.0 (full suite)
dotnet run --project CodroidTestNet8/CodroidTestNet8.csproj

# With controller IP
dotnet run --project CodroidTestNet8/CodroidTestNet8.csproj -- 192.168.8.10

# Specific demo
dotnet run --project CodroidTestNet8/CodroidTestNet8.csproj -- cri 192.168.8.10
dotnet run --project CodroidTestNet8/CodroidTestNet8.csproj -- io 192.168.8.10
dotnet run --project CodroidTestNet8/CodroidTestNet8.csproj -- register 192.168.8.10

# net462 / .NET Framework 4.6.2
dotnet run --project CodroidTestNet462/CodroidTestNet462.csproj -- 192.168.8.10
```

Error Handling

All TCP commands throw on failure:

Exception	Condition
CodroidCommandException	Controller returns <code>err</code>
TimeoutException	No response within 10 seconds
ArgumentException	Invalid parameter (SDK-side validation)

2. Core Concepts

CodroidClient Lifecycle

```
new CodroidClient(ip)
    |
    v
Connect()  --or--  ConnectRemoteAndSwitchOn()
    |
    v
[ IO / Register / Motion / CRI ... ]
    |
    v
Disconnect()
```

```
var robot = new CodroidClient("192.168.8.136");

try
{
    await robot.ConnectRemoteAndSwitchOn();
    // ... use robot ...
}
finally
{
    robot.Disconnect(); // Always call in finally
}
```

Constructor

```
var robot = new CodroidClient(string ip);
```

- `ip` -- Controller IP address
- TCP port is fixed at **9001**

Properties

Property	Type	Description
<code>CriData</code>	<code>CriRealTimeData</code>	Thread-safe clone of CRI data snapshot
<code>Data</code>	<code>CriRealTimeData</code>	Direct reference to internal CRI buffer (faster, not thread-safe)

Event

```
robot.CriDataReceived += data =>
{
    Console.WriteLine($"Joints: {string.Join(", ", data.JointPosition)}");
};
```

Fires after each valid CRI UDP frame is parsed. The `data` parameter is a thread-safe clone.

TCP Command Model

Every SDK method that talks to the controller follows this pattern:

1. SDK assigns a unique `id`
2. SDK serializes `{ id, ty, db }` as JSON and sends over TCP
3. Controller responds with `{ id, ty, db, err }`
4. SDK matches the response by `id`
5. If `err` is non-empty, throw `CodroidCommandException`
6. If no response in 10s, throw `TimeoutException`

CommonResponse

```
public class CommonResponse
{
    public object? id { get; set; }    // Request ID
    public string? ty { get; set; }    // Response type
    public JsonElement db { get; set; } // Business data
    public string? err { get; set; }   // Error message
}
```

Most methods return `Task<CommonResponse>`. The `db` field contains the actual result data.

Unit Convention

SDK public APIs use **mm** and **degrees**. This matches the TCP JSON protocol.

Context	Linear	Angular
SDK API, TCP JSON	mm	deg
CRI UDP wire format	m	rad
<code>CriRealTimeData</code> (parsed)	mm	deg

Important: CRI UDP binary payloads use meters and radians. The SDK automatically converts to mm/deg in `CriRealtimePacketParser.Parse()` and `CriRealtimeDispatcher` (with `convertToSi=true`). Do not assume raw UDP floats are in mm/deg.

Async Naming Convention

All public methods return `Task` or `Task<T>` but do **not** use the `Async` suffix.

```
// These are async methods -- await them
await robot.ConnectRemoteAndSwitchOn();
int di = await robot.GetDi(0);
await robot.MovJ(JointPoint.Degrees(joints), 40, 100);
```

This design keeps the same API names across C#, Python, and C++ SDKs.

Exception Types

Exception	When	Source
CodroidCommandException	Controller returns <code>err</code> field	TCP response
TimeoutException	No response within 10 seconds	TCP wait
ArgumentException	Invalid parameter value	SDK validation
ArgumentOutOfRangeException	Parameter out of range (e.g. DO port)	SDK validation
InvalidOperationException	Not connected	SDK state
ObjectDisposedException	Object already disposed	SDK state

CodroidCommandException Properties

```
public class CodroidCommandException : Exception
{
    public int RequestId { get; }          // Protocol request ID
    public string CommandType { get; }     // e.g. "Robot/move"
    public string? ControllerError { get; } // err field from controller
    public CommonResponse? Response { get; } // Full response
}
```

Thread Safety

- `CriData` -- Thread-safe (returns a clone)
- `Data` -- Not thread-safe (direct reference)
- All TCP methods -- Safe to call from any thread, but do not call concurrently on the same `CodroidClient`
- `CriRealtimeDispatcher` -- `SendCommand` / `SendTrajectory` are not thread-safe

3. CodroidClient API Reference

Class: CodroidClient

Namespace: Codroid

Source: CodroidSDK/Codroid.cs

Constructor

```
public CodroidClient(string ip)
```

Parameter	Type	Description
ip	string	Controller IP address

TCP port is fixed at **9001**.

```
var robot = new CodroidClient("192.168.8.136");
```

Properties

Property	Type	Description
CriData	CriRealTimeData	Thread-safe clone of CRI data snapshot
Data	CriRealTimeData	Direct reference to internal CRI buffer (faster, not thread-safe)

```
// Thread-safe (returns clone)
double[] joints = robot.CriData.JointPosition;

// Direct reference (faster)
double[] joints2 = robot.Data.JointPosition;
```

Event

```
public event Action<CriRealTimeData>? CriDataReceived
```

Fires after each valid CRI UDP frame is parsed. The parameter is a thread-safe clone.

```
robot.CriDataReceived += data =>
{
    Console.WriteLine($"Joints: {string.Join(", ", data.JointPosition)}");
    Console.WriteLine($"TCP: {string.Join(", ", data.TcpPose)}");
    Console.WriteLine($"InMotion: {data.InMotion}");
};
```

1. Connection Management

Connect

```
public async Task Connect()
```

Establishes TCP connection to the controller.

```
await robot.Connect();
```

Returns: Task — no return value

Throws: `CodroidCommandException` (controller error), `TimeoutException` (no response within 10s)

ConnectRemoteAndSwitchOn

```
public async Task ConnectRemoteAndSwitchOn()
```

Connects TCP, enters remote mode via auto, then powers on. This is the recommended one-call setup.

```
await robot.ConnectRemoteAndSwitchOn();
```

Returns: Task — no return value

Throws: `CodroidCommandException` (controller error), `TimeoutException` (no response within 10s)

Disconnect

```
public void Disconnect()
```

Stops CRI UDP listener and disconnects TCP. Always call in `finally` .

```
try
{
    await robot.ConnectRemoteAndSwitchOn();
    // ... operations ...
}
finally
{
    robot.Disconnect();
}
```

Returns: void

Throws: none

2. Mode Switching

SwitchOn / SwitchOff

```
public async Task<CommonResponse> SwitchOn()
public async Task<CommonResponse> SwitchOff()
```

Power on / power off the robot.

```
await robot.SwitchOn();  
// ... operations ...  
await robot.SwitchOff();
```

Returns: `Task<CommonResponse>` — controller response

Throws: `CodroidCommandException` (controller error), `TimeoutException` (no response within 10s)

ToManual/ToAuto/ToRemote

```
public Task<CommonResponse> ToManual()  
public Task<CommonResponse> ToAuto()  
public Task<CommonResponse> ToRemote()
```

Switch to manual / auto / remote mode. Requires firmware 2.3.2.6+.

Returns: `Task<CommonResponse>` — controller response

Throws: `CodroidCommandException` (controller error), `TimeoutException` (no response within 10s)

EnterManualModeViaAuto/EnterRemoteModeViaAuto

```
public async Task<CommonResponse> EnterManualModeViaAuto()  
public async Task<CommonResponse> EnterRemoteModeViaAuto()
```

Switches to auto first, then to manual / remote. Satisfies the controller's "must go through auto" restriction.

```
await robot.EnterRemoteModeViaAuto();
```

Returns: `Task<CommonResponse>` — controller response

Throws: `CodroidCommandException` (controller error), `TimeoutException` (no response within 10s)

ToSimulation / ToActual

```
public Task<CommonResponse> ToSimulation()  
public Task<CommonResponse> ToActual()
```

Switch to simulation / real-machine mode.

Returns: Task<CommonResponse> — controller response

Throws: CodroidCommandException (controller error), TimeoutException (no response within 10s)

StartDrag / StopDrag

```
public Task<CommonResponse> StartDrag()  
public Task<CommonResponse> StopDrag()
```

Enter / exit drag mode. Requires firmware 2.3.2.6+.

Returns: Task<CommonResponse> — controller response

Throws: CodroidCommandException (controller error), TimeoutException (no response within 10s)

ClearSystemError

```
public Task<CommonResponse> ClearSystemError()
```

Clears the system error state.

Returns: Task<CommonResponse> — controller response

Throws: CodroidCommandException (controller error), TimeoutException (no response within 10s)

3. Motion Commands (Non-Blocking)

All motion methods send the command and return immediately. Use `*Sync` variants for blocking wait.

MovJ -- Joint Move

```
public Task<CommonResponse> MovJ(JointPoint target, double speed, double acc,
    double? blend = null, double[]? coor = null, double[]? tool = null, double?
    relativeBlend = null)

public Task<CommonResponse> MovJ(CartesianPoint target, double speed, double acc,
    double? blend = null, double[]? coor = null, double[]? tool = null, double?
    relativeBlend = null)
```

Parameter	Type	Default	Description
target	JointPoint / CartesianPoint	--	Target position
speed	double	--	Speed
acc	double	--	Acceleration
blend	double?	null	Blend radius. Mutually exclusive with <code>relativeBlend</code> — if both set, <code>relativeBlend</code> is ignored. Omit for no transition
coor	double[]?	null	User coordinate frame. <code>null</code> = omitted from command
tool	double[]?	null	Tool coordinate frame. <code>null</code> = omitted from command
relativeBlend	double?	null	Relative blend ratio (0–100). Mutually exclusive with <code>blend</code> — if both set, this is ignored

Returns: `Task<CommonResponse>` — controller response

Throws: `CodroidCommandException` (controller error), `TimeoutException` (no response within 10s)

```
// Joint target
await robot.MovJ(JointPoint.Degrees(new[] { 0, 0, 90, 0, 90, 0 })), speed: 40, acc:
100);

// Cartesian target (joint motion to TCP pose)
await robot.MovJ(CartesianPoint.MmDeg(new[] { 400, 0, 300, 180, 0, 0 })), speed: 40,
acc: 100);
```

MovL -- Linear Move

```
public Task<CommonResponse> MovL(CartesianPoint target, double speed, double acc,
    double? blend = null, double[]? coor = null, double[]? tool = null, double?
relativeBlend = null)

public Task<CommonResponse> MovL(JointPoint target, double speed, double acc,
    double? blend = null, double[]? coor = null, double[]? tool = null, double?
relativeBlend = null)
```

Parameter	Type	Default	Description
target	CartesianPoint / JointPoint	—	Target position
speed	double	—	Speed (mm/s)
acc	double	—	Acceleration
blend	double?	null	Blend radius. Mutually exclusive with <code>relativeBlend</code> — if both set, <code>relativeBlend</code> is ignored. Omit for no transition
coor	double[]?	null	User coordinate frame. <code>null</code> = omitted from command
tool	double[]?	null	Tool coordinate frame. <code>null</code> = omitted from command

Parameter	Type	Default	Description
<code>relativeBlend</code>	<code>double?</code>	<code>null</code>	Relative blend ratio (0–100). Mutually exclusive with <code>blend</code> — if both set, this is ignored

Returns: `Task<CommonResponse>` — controller response

Throws: `CodroidCommandException` (controller error), `TimeoutException` (no response within 10s)

```
// Cartesian linear move
await robot.MovL(CartesianPoint.MmDegWithRef(pose, robot.CriData.JointPosition),
    speed: 150, acc: 500);

// Linear move to joint target
await robot.MovL(JointPoint.Degrees(new[] { 10, 20, 90, 0, 90, 0 }), speed: 100, acc:
    300);
```

MovC -- Circular Move

```
public Task<CommonResponse> MovC(CartesianPoint middle, CartesianPoint target,
    double speed, double acc, double? blend = null,
    double[]? coor = null, double[]? tool = null, double? relativeBlend = null)
```

Parameter	Type	Default	Description
<code>middle</code>	<code>CartesianPoint</code>	—	Intermediate point (on arc)
<code>target</code>	<code>CartesianPoint</code>	—	End point
<code>speed</code>	<code>double</code>	—	Speed (mm/s)
<code>acc</code>	<code>double</code>	—	Acceleration
<code>blend</code>	<code>double?</code>	<code>null</code>	Blend radius. Mutually exclusive with <code>relativeBlend</code> — if both set, <code>relativeBlend</code> is ignored. Omit for no transition

Parameter	Type	Default	Description
<code>coord</code>	<code>double[]?</code>	<code>null</code>	User coordinate frame. <code>null</code> = omitted from command
<code>tool</code>	<code>double[]?</code>	<code>null</code>	Tool coordinate frame. <code>null</code> = omitted from command
<code>relativeBlend</code>	<code>double?</code>	<code>null</code>	Relative blend ratio (0–100). Mutually exclusive with <code>blend</code> — if both set, this is ignored

Returns: `Task<CommonResponse>` — controller response

Throws: `CodroidCommandException` (controller error), `TimeoutException` (no response within 10s)

```
await robot.MovC(
    CartesianPoint.MmDeg(new[] { 450, 100, 300, 180, 0, 0 }),
    CartesianPoint.MmDeg(new[] { 500, 0, 300, 180, 0, 0 }),
    speed: 100, acc: 300);
```

MovCircle -- Full Circle Move

```
public Task<CommonResponse> MovCircle(CartesianPoint middle, CartesianPoint target,
    int circleNum, double speed, double acc, double? blend = null,
    double[]? coord = null, double[]? tool = null, double? relativeBlend = null)
```

Parameter	Type	Default	Description
<code>middle</code>	<code>CartesianPoint</code>	—	Intermediate point
<code>target</code>	<code>CartesianPoint</code>	—	End point
<code>circleNum</code>	<code>int</code>	—	Number of full circles
<code>speed</code>	<code>double</code>	—	Speed (mm/s)
<code>acc</code>	<code>double</code>	—	Acceleration

Parameter	Type	Default	Description
<code>blend</code>	<code>double?</code>	<code>null</code>	Blend radius. Mutually exclusive with <code>relativeBlend</code> — if both set, <code>relativeBlend</code> is ignored. Omit for no transition
<code>coord</code>	<code>double[]?</code>	<code>null</code>	User coordinate frame. <code>null</code> = omitted from command
<code>tool</code>	<code>double[]?</code>	<code>null</code>	Tool coordinate frame. <code>null</code> = omitted from command
<code>relativeBlend</code>	<code>double?</code>	<code>null</code>	Relative blend ratio (0–100). Mutually exclusive with <code>blend</code> — if both set, this is ignored

Returns: `Task<CommonResponse>` — controller response

Throws: `CodroidCommandException` (controller error), `TimeoutException` (no response within 10s)

```
await robot.MovCircle(
    CartesianPoint.MmDeg(mid),
    CartesianPoint.MmDeg(end),
    circleNum: 1, speed: 80, acc: 200);
```

Move -- Multi-Segment Path

```
public async Task<CommonResponse> Move(IReadOnlyList<MoveInstruction> instructions)
```

Sends a list of motion instructions as a single path command.

Parameter	Type	Default	Description
<code>instructions</code>	<code>IReadOnlyList<MoveInstruction></code>	—	List of move instructions

Returns: `Task<CommonResponse>` — controller response

Throws: `CodroidCommandException` (controller error), `TimeoutException` (no response within 10s)

```
await robot.Move(new[]
{
    MoveInstruction.MovJ(JointPoint.Degrees(new[] { 0, 0, 90, 0, 90, 0 })), 40, 100),
    MoveInstruction.MovL(CartesianPoint.MmDegWithRef(pose,
robot.CriData.JointPosition), 150, 500),
    MoveInstruction.MovC(CartesianPoint.MmDeg(mid), CartesianPoint.MmDeg(end), 100,
300),
});
```

4. Blocking Motion Commands

`*Sync` methods send the motion command, then **block until CRI confirms the robot has reached the target**. They return `true` on success, or throw on error/timeout.

Prerequisite: `StartCriDataPush` must be active.

MovJSync

```
public bool MovJSync(JointPoint target, double speed, double acc,
    MotionWaitOptions? wait = null, double? blend = null,
    double[]? coor = null, double[]? tool = null, double? relativeBlend = null)

public bool MovJSync(CartesianPoint target, double speed, double acc,
    MotionWaitOptions? wait = null, double? blend = null,
    double[]? coor = null, double[]? tool = null, double? relativeBlend = null)
```

Parameter	Type	Default	Description
<code>target</code>	<code>JointPoint</code> / <code>CartesianPoint</code>	—	Target position
<code>speed</code>	<code>double</code>	—	Speed (deg/s)
<code>acc</code>	<code>double</code>	—	Acceleration
<code>wait</code>	<code>MotionWaitOptions?</code>	<code>null</code>	Wait options (timeout, tolerance, etc.)

Parameter	Type	Default	Description
<code>blend</code>	<code>double?</code>	<code>null</code>	Blend radius. Mutually exclusive with <code>relativeBlend</code> — if both set, <code>relativeBlend</code> is ignored. Omit for no transition
<code>coor</code>	<code>double[]?</code>	<code>null</code>	User coordinate frame. <code>null</code> = omitted from command
<code>tool</code>	<code>double[]?</code>	<code>null</code>	Tool coordinate frame. <code>null</code> = omitted from command
<code>relativeBlend</code>	<code>double?</code>	<code>null</code>	Relative blend ratio (0–100). Mutually exclusive with <code>blend</code> — if both set, this is ignored

Returns: `bool` — `true` when target is reached

Throws:

- `TimeoutException` — motion timed out (controlled by `MotionWaitOptions.Timeout`)
- `InvalidOperationException` — robot in abnormal state (collision, E-stop, alarm) or stopped without reaching target

```
var wait = new MotionWaitOptions
{
    Timeout = TimeSpan.FromSeconds(90),
    JointToleranceDeg = 0.3
};

robot.MovJSync(JointPoint.Degrees(new[] { 0, 0, 90, 0, 90, 0 }), 40, 100, wait);
```

MovLSync

```
public bool MovLSync(CartesianPoint target, double speed, double acc,
    MotionWaitOptions? wait = null, double? blend = null,
    double[]? coor = null, double[]? tool = null, double? relativeBlend = null)

public bool MovLSync(JointPoint target, double speed, double acc,
    MotionWaitOptions? wait = null, double? blend = null,
    double[]? coor = null, double[]? tool = null, double? relativeBlend = null)
```

Parameter	Type	Default	Description
target	CartesianPoint / JointPoint	—	Target position
speed	double	—	Speed (mm/s)
acc	double	—	Acceleration
wait	MotionWaitOptions?	null	Wait options
blend	double?	null	Blend radius. Mutually exclusive with <code>relativeBlend</code> — if both set, <code>relativeBlend</code> is ignored. Omit for no transition
coor	double[]?	null	User coordinate frame. <code>null</code> = omitted from command
tool	double[]?	null	Tool coordinate frame. <code>null</code> = omitted from command
relativeBlend	double?	null	Relative blend ratio (0–100). Mutually exclusive with <code>blend</code> — if both set, this is ignored

Returns: `bool` — `true` when target is reached

Throws: `TimeoutException` (motion timeout), `InvalidOperationException` (abnormal state or target not reached)


```
robot.MovLSync(
    CartesianPoint.MmDegWithRef(pose, robot.CriData.JointPosition),
    speed: 150, acc: 500,
    wait: new MotionWaitOptions
    {
        Timeout = TimeSpan.FromSeconds(60),
        CartesianPositionToleranceMm = 2.0,
        CartesianOrientationToleranceDeg = 1.5
    });
```

MovCSync

```
public bool MovCSync(CartesianPoint middle, CartesianPoint target,
    double speed, double acc, MotionWaitOptions? wait = null,
    double? blend = null, double[]? coor = null, double[]? tool = null, double?
    relativeBlend = null)
```

Parameter	Type	Default	Description
middle	CartesianPoint	—	Intermediate point (on arc)
target	CartesianPoint	—	End point
speed	double	—	Speed (mm/s)
acc	double	—	Acceleration
wait	MotionWaitOptions?	null	Wait options
blend	double?	null	Blend radius. Mutually exclusive with <code>relativeBlend</code> — if both set, <code>relativeBlend</code> is ignored. Omit for no transition
coor	double[]?	null	User coordinate frame. <code>null</code> = omitted from command
tool	double[]?	null	Tool coordinate frame. <code>null</code> = omitted from command

Parameter	Type	Default	Description
<code>relativeBlend</code>	<code>double?</code>	<code>null</code>	Relative blend ratio (0–100). Mutually exclusive with <code>blend</code> — if both set, this is ignored

Returns: `bool` — `true` when target is reached

Throws: `TimeoutException` (motion timeout), `InvalidOperationException` (abnormal state or target not reached)

```
robot.MovCSync(
    CartesianPoint.MmDeg(mid), CartesianPoint.MmDeg(end),
    speed: 100, acc: 300);
```

MovCircleSync

```
public bool MovCircleSync(CartesianPoint middle, CartesianPoint target,
    int circleNum, double speed, double acc, MotionWaitOptions? wait = null,
    double? blend = null, double[]? coor = null, double[]? tool = null, double?
    relativeBlend = null)
```

Parameter	Type	Default	Description
<code>middle</code>	<code>CartesianPoint</code>	—	Intermediate point
<code>target</code>	<code>CartesianPoint</code>	—	End point
<code>circleNum</code>	<code>int</code>	—	Number of full circles
<code>speed</code>	<code>double</code>	—	Speed (mm/s)
<code>acc</code>	<code>double</code>	—	Acceleration
<code>wait</code>	<code>MotionWaitOptions?</code>	<code>null</code>	Wait options
<code>blend</code>	<code>double?</code>	<code>null</code>	Blend radius. Mutually exclusive with <code>relativeBlend</code> — if both set, <code>relativeBlend</code> is ignored. Omit for no transition

Parameter	Type	Default	Description
<code>coord</code>	<code>double[]?</code>	<code>null</code>	User coordinate frame. <code>null</code> = omitted from command
<code>tool</code>	<code>double[]?</code>	<code>null</code>	Tool coordinate frame. <code>null</code> = omitted from command
<code>relativeBlend</code>	<code>double?</code>	<code>null</code>	Relative blend ratio (0–100). Mutually exclusive with <code>blend</code> — if both set, this is ignored

Returns: `bool` — `true` when target is reached

Throws: `TimeoutException` (motion timeout), `InvalidOperationException` (abnormal state or target not reached)

MoveSync

```
public bool MoveSync(IReadOnlyList<MoveInstruction> instructions, MotionWaitOptions? wait = null)
```

Sends multi-segment path and blocks until the last segment target is reached.

Parameter	Type	Default	Description
<code>instructions</code>	<code>IReadOnlyList<MoveInstruction></code>	—	List of move instructions
<code>wait</code>	<code>MotionWaitOptions?</code>	<code>null</code>	Wait options

Returns: `bool` — `true` when target is reached

Throws: `TimeoutException` (motion timeout), `InvalidOperationException` (abnormal state or target not reached)

```
robot.MoveSync(new[]  
{  
    MoveInstruction.MovJ(JointPoint.Degrees(j1), 40, 100),  
    MoveInstruction.MovL(CartesianPoint.MmDegWithRef(p2, refJ), 150, 500),  
});
```

5. Motion Control

PauseRobotMotion

```
public async Task<CommonResponse> PauseRobotMotion()
```

Pauses the current motion.

Returns: `Task<CommonResponse>` — controller response

Throws: `CodroidCommandException` (controller error), `TimeoutException` (no response within 10s)

ResumeRobotMotion

```
public async Task<CommonResponse> ResumeRobotMotion()
```

Resumes paused motion.

Returns: `Task<CommonResponse>` — controller response

Throws: `CodroidCommandException` (controller error), `TimeoutException` (no response within 10s)

StopRobotMove

```
public async Task<CommonResponse> StopRobotMove()
```

Stops the current motion immediately.

Returns: `Task<CommonResponse>` — controller response

Throws: `CodroidCommandException` (controller error), `TimeoutException` (no response within 10s)

6. MoveTo Commands

MoveTo

```
public async Task<CommonResponse> MoveTo(MoveToKind kind, MoveToTarget? target = null)
```

Moves to a preset or planned position. Requires heartbeat while running.

Parameter	Type	Default	Description
kind	<code>MoveToKind</code>	—	Target type (Home, Safe, JointPlanned, etc.)
target	<code>MoveToTarget?</code>	null	Planned target (only for JointPlanned/LinePlanned)

Returns: `Task<CommonResponse>` — controller response

Throws: `CodroidCommandException` (controller error), `TimeoutException` (no response within 10s)

```
// Move to home position
await robot.MoveTo(MoveToKind.Home);

// Move to safe position
await robot.MoveTo(MoveToKind.Safe);

// Move to specific joint position
await robot.MoveTo(MoveToKind.JointPlanned,
MoveToTarget.Joint(JointPoint.Degrees(joints)));
```

MoveToHeartbeat

```
public async Task<CommonResponse> MoveToHeartbeat()
```

Sends heartbeat to maintain MoveTo motion. Call at ~500ms intervals.

Returns: Task<CommonResponse> — controller response

Throws: CodroidCommandException (controller error), TimeoutException (no response within 10s)

StopMoveTo

```
public async Task<CommonResponse> StopMoveTo()
```

Stops the current MoveTo / RunTo motion.

Returns: Task<CommonResponse> — controller response

Throws: CodroidCommandException (controller error), TimeoutException (no response within 10s)

7. Jog Commands

StartJog

```
public async Task<CommonResponse> StartJog(RobotJogParameters parameters)
```

Starts jogging. Requires heartbeat at ~500ms intervals.

Parameter	Type	Default	Description
parameters	RobotJogParameters	—	Jog parameters (mode, speed, axis index, coordinate frame)

Returns: Task<CommonResponse> — controller response

Throws: CodroidCommandException (controller error), TimeoutException (no response within 10s)

```
var jogParams = RobotJogParameters.Create(  
    RobotJogMode.Joint,    // Joint mode  
    speed: 10,             // Speed  
    index: 0,              // Axis index (0-5)  
    RobotJogFrameType.User, // User frame  
    coordId: 0             // Coordinate ID  
);  
  
await robot.StartJog(jogParams);  
  
// Keep sending heartbeat  
while (jogging)  
{  
    await Task.Delay(500);  
    await robot.JogHeartbeat();  
}  
  
await robot.StopJog();
```

StopJog

```
public async Task<CommonResponse> StopJog()
```

Stops jogging.

Returns: Task<CommonResponse> — controller response

Throws: CodroidCommandException (controller error), TimeoutException (no response within 10s)

JogHeartbeat

```
public async Task<CommonResponse> JogHeartbeat()
```

Sends heartbeat to maintain jog state. Call at ~500ms intervals.

Returns: `Task<CommonResponse>` — controller response

Throws: `CodroidCommandException` (controller error), `TimeoutException` (no response within 10s)

8. IO Operations

GetDi/GetDo/GetAi/GetAo

```
public async Task<int> GetDi(int port)      // Read DI
public async Task<int> GetDo(int port)      // Read DO
public async Task<double> GetAi(int port)    // Read AI
public async Task<double> GetAo(int port)    // Read AO
```

Parameter	Type	Default	Description
port	int	—	IO port number

Returns: `GetDi / GetDo` → `Task<int>` (0 or 1); `GetAi / GetAo` → `Task<double>`

Throws: `CodroidCommandException` (controller error), `TimeoutException` (no response within 10s)

```
int di0 = await robot.GetDi(0);
Console.WriteLine($"DI 0 = {di0}");

double ai1 = await robot.GetAi(1);
Console.WriteLine($"AI 1 = {ai1:F3}");
```

SetDo/SetAo

```
public async Task<CommonResponse> SetDo(int port, int value)    // Write DO (0 or 1)
public async Task<CommonResponse> SetAo(int port, double value) // Write AO
```

Parameter	Type	Default	Description
port	int	—	IO port number

Parameter	Type	Default	Description
value	int / double	—	Value to write (SetDo : 0 or 1; SetAo : floating-point)

Returns: Task<CommonResponse> — controller response

Throws: CodroidCommandException (controller error), TimeoutException (no response within 10s), ArgumentOutOfRangeException (SetDo value not 0 or 1)

```
await robot.SetDo(10, 1); // Set D0 10 high
await robot.SetDo(10, 0); // Set D0 10 low
await robot.SetAo(0, 3.14); // Set A0 0 to 3.14
```

GetIoValues (Batch Read)

```
public async Task<CommonResponse> GetIoValues(IReadOnlyList<(string Type, int Port)> pins)
```

Parameter	Type	Default	Description
pins	IReadOnlyList<(string Type, int Port)>	—	IO pin list, Type: "DI" / "DO" / "AI" / "AO"

Returns: Task<CommonResponse> — results in resp.db

Throws: CodroidCommandException (controller error), TimeoutException (no response within 10s)

```
var pins = new (string Type, int Port)[]
{
    ("DI", 0), ("DI", 1), ("DO", 10), ("AI", 0)
};

CommonResponse resp = await robot.GetIoValues(pins);
// Results in resp.db
```

9. Register Operations

GetRegisterValue

```
public async Task<RegisterReadValue> GetRegisterValue(int address)
```

Parameter	Type	Default	Description
address	int	—	Register address

Returns: Task<RegisterReadValue> — contains address and raw JSON value, use `GetInt32()` / `GetDouble()` to convert

Throws: `CodroidCommandException` (controller error), `TimeoutException` (no response within 10s)

```
RegisterReadValue reg = await robot.GetRegisterValue(49100);  
int intVal = reg.GetInt32();  
double dblVal = reg.GetDouble();
```

GetRegisterValues (Batch Read)

```
public async Task<IReadOnlyList<RegisterReadValue>>  
GetRegisterValues(IReadOnlyList<int> addresses)
```

Parameter	Type	Default	Description
addresses	IReadOnlyList<int>	—	List of register addresses

Returns: Task<IReadOnlyList<RegisterReadValue>> — register values in same order as input addresses

Throws: `CodroidCommandException` (controller error), `TimeoutException` (no response within 10s)

```
var addresses = new[] { 49100, 49101, 49102 };
IReadOnlyList<RegisterReadValue> values = await robot.GetRegisterValues(addresses);

for (int i = 0; i < values.Count; i++)
    Console.WriteLine($"Register {addresses[i]} = {values[i].GetInt32()}");
```

SetRegisterValue

```
public async Task<CommonResponse> SetRegisterValue(int address, int value)
public async Task<CommonResponse> SetRegisterValue(int address, double value)
```

```
await robot.SetRegisterValue(49100, 42);
await robot.SetRegisterValue(49101, 3.14);
```

SetExtendArrayType / RemoveExtendArray

```
public async Task<CommonResponse> SetExtendArrayType(int index, string type)
public async Task<CommonResponse> RemoveExtendArray(int index)
```

Manage extend-array elements (index 0~999).

```
await robot.SetExtendArrayType(0, RegisterExtendArrayValueType.Int32);
await robot.RemoveExtendArray(0);
```

10. Robot Settings (19.x Protocol)

SetManualMoveRate / SetAutoMoveRate

```
public async Task<CommonResponse> SetManualMoveRate(int percent)
public async Task<CommonResponse> SetAutoMoveRate(int percent)
```

Set manual / auto motion rate (1~100%).

Parameter	Type	Default	Description
percent	int	--	Motion rate percentage (1~100)

Returns: `Task<CommonResponse>` — controller response

Throws: `CodroidCommandException` (controller error), `TimeoutException` (no response within 10s), `ArgumentOutOfRangeException` (percent out of range)

```
await robot.SetManualMoveRate(50); // 50% speed
await robot.SetAutoMoveRate(100); // Full speed
```

SetCollisionSensitivity

```
public async Task<CommonResponse> SetCollisionSensitivity(int sensitivity)
```

Set collision detection sensitivity (0~100). Firmware 2.3.2.10+.

Parameter	Type	Default	Description
sensitivity	int	--	Collision detection sensitivity (0~100)

Returns: `Task<CommonResponse>` — controller response

Throws: `CodroidCommandException` (controller error), `TimeoutException` (no response within 10s), `ArgumentOutOfRangeException` (sensitivity out of range)

```
await robot.SetCollisionSensitivity(50);
```

SetPayload

```
public async Task<CommonResponse> SetPayload(int payloadId)
```

Set active payload slot (0~15). Firmware 2.3.2.10+.

Parameter	Type	Default	Description
payloadId	int	--	Active payload slot ID (0~15)

Returns: `Task<CommonResponse>` — controller response

Throws: `CodroidCommandException` (controller error), `TimeoutException` (no response within 10s), `ArgumentOutOfRangeException` (payloadId out of range)

```
await robot.SetPayload(1); // Use payload slot 1
```

GetRobotParameters

```
public async Task<RobotParameters> GetRobotParameters()
```

Gets all setting-interface parameters (protocol 19.7). Returns tool frames, payload frames, coordinate frames, and default IDs.

Returns: `Task<RobotParameters>` — robot parameters including tool frames, payload frames, coordinate frames, and default IDs

Throws: `CodroidCommandException` (controller error), `TimeoutException` (no response within 10s)

```
RobotParameters param = await robot.GetRobotParameters();
Console.WriteLine($"Default Tool: {param.DefaultToolId}");
Console.WriteLine($"Default Payload: {param.DefaultPayloadId}");
Console.WriteLine($"Max Payload: {param.MaxPayload} kg");
```

SetDefaultPayloadId / SetDefaultToolId / SetDefaultUserCoordinateId

```
public Task<CommonResponse> SetDefaultPayloadId(int payloadId) // 0~15
public Task<CommonResponse> SetDefaultToolId(int toolId) // 0~15
public Task<CommonResponse> SetDefaultUserCoordinateId(int coordinateId) // 0~15
```

Set default payload / tool / user coordinate frame slot.

Parameter	Type	Default	Description
payloadId / toolId / coordinateId	int	--	Frame slot ID (0~15)

Returns: Task<CommonResponse> — controller response

Throws: CodroidCommandException (controller error), TimeoutException (no response within 10s),
ArgumentOutOfRangeException (id out of range)

```
await robot.SetDefaultToolId(2);
await robot.SetDefaultPayloadId(1);
await robot.SetDefaultUserCoordinateId(0);
```

SaveToolFrames / SetToolFrame

```
public Task<CommonResponse> SaveToolFrames(IReadOnlyList<RobotFrame> frames)
public async Task<CommonResponse> SetToolFrame(int frameId, RobotFrame frame)
```

Save the full tool frame table (must include id 0~15, id=0 must be all zeros) / Modify a single tool frame (read-then-write, id 1~15 only).

Method	Parameter	Type	Default	Description
SaveToolFrames	frames	IReadOnlyList<RobotFrame>	--	Complete tool frame table (id 0~15, id=0 must be all zeros)
SetToolFrame	frameId	int	--	Tool frame ID (1~15)
	frame	RobotFrame	--	Tool frame data

Returns: Task<CommonResponse> — controller response

Throws: CodroidCommandException (controller error), TimeoutException (no response within 10s)

```
// Set single tool frame
await robot.SetToolFrame(1, new RobotFrame
{
    Id = 1, X = 0, Y = 0, Z = 100, A = 0, B = 0, C = 0
});
```

SavePayloadFrames / SetPayloadFrame

```
public Task<CommonResponse> SavePayloadFrames(IReadOnlyList<RobotPayloadFrame> frames)
public async Task<CommonResponse> SetPayloadFrame(int frameId, RobotPayloadFrame
frame)
```

Save full payload frame table / Modify single payload frame (id 1~15).

Method	Parameter	Type	Default	Description
SavePayloadFrames	frames	IReadOnlyList<RobotPayloadFrame>	--	Complete payload frame table (id 0~15)
SetPayloadFrame	frameId	int	--	Payload frame ID (1~15)
	frame	RobotPayloadFrame	--	Payload frame data

Returns: Task<CommonResponse> — controller response

Throws: CodroidCommandException (controller error), TimeoutException (no response within 10s)

```
await robot.SetPayloadFrame(1, new RobotPayloadFrame
{
    Id = 1, M = 2.5, Mx = 0, My = 0, Mz = 50
});
```

SaveUserCoordinateFrames / SetUserCoordinateFrame

```
public Task<CommonResponse> SaveUserCoordinateFrames(IReadOnlyList<RobotFrame> frames)
public async Task<CommonResponse> SetUserCoordinateFrame(int frameId, RobotFrame
frame)
```

Save full user coordinate frame table / Modify single user coordinate frame (id 1~15).

Method	Parameter	Type	Default	Description
SaveUserCoordinateFrames	frames	IReadOnlyList<RobotFrame>	--	Complete user coordinate frame table (id 0~15)
SetUserCoordinateFrame	frameId	int	--	User coordinate frame ID (1~15)
	frame	RobotFrame	--	User coordinate frame data

Returns: Task<CommonResponse> — controller response

Throws: CodroidCommandException (controller error), TimeoutException (no response within 10s)

```
await robot.SetUserCoordinateFrame(1, new RobotFrame
{
    Id = 1, X = 100, Y = 200, Z = 0, A = 0, B = 0, C = 45
});
```

11. CRI Real-Time Data

StartCriDataPush

```
public async Task<CommonResponse> StartCriDataPush(string udpIp, int udpPort)
```

Starts local UDP listener and requests controller to push CRI real-time data. Fixed params: 100ms period, high-precision, mask 0xFFFF, 308-byte UDP packet.

Parameter	Type	Default	Description
udpIp	string	--	Local IP address to receive CRI UDP data
udpPort	int	--	Local UDP port number

Returns: Task<CommonResponse> — controller response

Throws: CodroidCommandException (controller error), TimeoutException (no response within 10s)

Method	Protocol
StartCriDataPush(udpIp, udpPort)	CRI/StartDataPush

```
await robot.StartCriDataPush("192.168.8.150", 18888);

robot.CriDataReceived += data =>
{
    Console.WriteLine($"Joints: {string.Join(", ", data.JointPosition)}");
};
```

StopCriDataPush

```
public async Task<CommonResponse> StopCriDataPush(string? udpIp = null, int? udpPort = null)
```

Requests controller to stop CRI data push and closes local UDP listener.

Parameter	Type	Default	Description
udpIp	string?	null	Local IP address (optional)
udpPort	int?	null	Local UDP port (optional)

Returns: Task<CommonResponse> — controller response

Throws: CodroidCommandException (controller error), TimeoutException (no response within 10s)

Method	Protocol
StopCriDataPush(ip, port)	CRI/StopDataPush

```
await robot.StopCriDataPush("192.168.8.150", 18888);
```

12. CRI Real-Time Control

StartCriControl

```
public async Task<CommonResponse> StartCriControl(int filterType = 1, int durationMs = 4, int startBuffer = 5)
```

Enables CRI real-time control mode.

Parameter	Type	Default	Description
filterType	int	1	0=off, 1=average, 2=2nd-order LP, 3=elliptic
durationMs	int	4	Control period (1~16ms, must divide 1000)
startBuffer	int	5	Start buffer frames (1~100)

Returns: Task<CommonResponse> — controller response

Throws: CodroidCommandException (controller error), TimeoutException (no response within 10s)

Method	Protocol
StartCriControl(...)	CRI/StartControl

```
await robot.StartCriControl(filterType: 1, durationMs: 4, startBuffer: 5);
```

StopCriControl

```
public async Task<CommonResponse> StopCriControl()
```

Disables CRI real-time control mode.

Returns: Task<CommonResponse> — controller response

Throws: CodroidCommandException (controller error), TimeoutException (no response within 10s)

Method	Protocol
StopCriControl()	CRI/StopControl

13. Project Execution

EnterRemoteScriptMode

```
public async Task<CommonResponse> EnterRemoteScriptMode()
```

Requests entering remote script mode.

Method	Protocol
EnterRemoteScriptMode()	project/enterRemoteScriptMode

Returns: Task<CommonResponse> — controller response

Throws: CodroidCommandException (controller error), TimeoutException (no response within 10s)

RunScript

```
public async Task<CommonResponse> RunScript(  
    string mainScript,  
    IReadOnlyDictionary<string, string>? subThreads = null,  
    IReadOnlyDictionary<string, string>? subPrograms = null,  
    IReadOnlyDictionary<string, string>? interrupts = null,  
    IReadOnlyDictionary<string, object>? vars = null)
```

Sends a script for immediate execution.

Parameter	Type	Default	Description
mainScript	string	--	Main script content to execute
subThreads	IReadOnlyDictionary<string, string>?	null	Sub-thread scripts keyed by name
subPrograms	IReadOnlyDictionary<string, string>?	null	Sub-program scripts keyed by name
interrupts	IReadOnlyDictionary<string, string>?	null	Interrupt handler scripts keyed by name
vars	IReadOnlyDictionary<string, object>?	null	Initial variable values keyed by name

Returns: Task<CommonResponse> — controller response

Throws: CodroidCommandException (controller error), TimeoutException (no response within 10s)

```
await robot.RunScript(mainScript: "movej(j1, v50) sub1() end");
```

Run / RunByIndex / RunStep

```
public async Task<CommonResponse> Run(string projectID)  
public async Task<CommonResponse> RunByIndex(int index)  
public async Task<CommonResponse> RunStep(string projectID)
```

Start a project by ID / index / single-step.

`Run(string projectID)`

Parameter	Type	Default	Description
projectID	string	--	Project identifier to run

`RunByIndex(int index)`

Parameter	Type	Default	Description
index	int	--	Project index to run

`RunStep(string projectID)`

Parameter	Type	Default	Description
projectID	string	--	Project identifier to run in single-step mode

Returns: `Task<CommonResponse>` — controller response

Throws: `CodroidCommandException` (controller error), `TimeoutException` (no response within 10s)

```
await robot.Run("project_001");
await robot.RunByIndex(0);
await robot.RunStep("project_001");
```

PauseProject / ResumeProject / StopProject

```
public async Task<CommonResponse> PauseProject()
public async Task<CommonResponse> ResumeProject()
public async Task<CommonResponse> StopProject()
```

Method	Protocol
PauseProject()	project/pause

Method	Protocol
<code>ResumeProject()</code>	<code>project/resume</code>
<code>StopProject()</code>	<code>project/stop</code>

Returns: `Task<CommonResponse>` — controller response

Throws: `CodroidCommandException` (controller error), `TimeoutException` (no response within 10s)

14. Publish/Subscribe

SubscribePublishTopic

```
public async Task<PublishTopicSubscription> SubscribePublishTopic(
    string topicTy, Action<PublishNotification> handler, int tcMilliseconds = 100)
```

Subscribes to a TCP topic push. Returns a disposable subscription handle.

Parameter	Type	Default	Description
<code>topicTy</code>	<code>string</code>	--	Topic name, e.g. <code>PublishTopics.RobotStatus</code>
<code>handler</code>	<code>Action<PublishNotification></code>	--	Callback to process notifications; should not block for long
<code>tcMilliseconds</code>	<code>int</code>	100	Protocol <code>tc</code> field in milliseconds

Returns: `Task<PublishTopicSubscription>` — disposable subscription handle

Throws: `CodroidCommandException` (controller error), `TimeoutException` (no response within 10s)

```

using var sub = await robot.SubscribePublishTopic(
    PublishTopics.RobotStatus,
    notification =>
    {
        Console.WriteLine($"Topic: {notification.Ty}");
        Console.WriteLine($"Data: {notification.Db}");
    });

// Subscription active until sub.Dispose()
await Task.Delay(10000);
// sub.Dispose() called by 'using'

```

15. Global Variables

GetGlobalVars / GetGlobalVarsCatalog

```

public async Task<CommonResponse> GetGlobalVars()
public async Task<IReadOnlyDictionary<string, GlobalVarCatalogEntry>>
    GetGlobalVarsCatalog()

```

GetGlobalVars() — no parameters.

Returns: `Task<CommonResponse>` — controller response with all global variables in `db`

Throws: `CodroidCommandException` (controller error), `TimeoutException` (no response within 10s)

GetGlobalVarsCatalog() — no parameters.

Returns: `Task<IReadOnlyDictionary<string, GlobalVarCatalogEntry>>` — dictionary keyed by variable name

Throws: `CodroidCommandException` (controller error), `TimeoutException` (no response within 10s)

```
var catalog = await robot.GetGlobalVarsCatalog();
foreach (var (name, entry) in catalog)
{
    Console.WriteLine($"{name} = {entry.Value} ({entry.Remark})");
}
```

SaveGlobalVar/SaveGlobalVars

```
public Task<CommonResponse> SaveGlobalVar(string name, object value, string? remark = null)
public async Task<CommonResponse>
SaveGlobalVars(IReadOnlyCollection<GlobalVarSaveItem> items)
```

SaveGlobalVar(string name, object value, string? remark = null)

Parameter	Type	Default	Description
name	string	--	Variable name (validated by <code>GlobalVarNaming.Validate()</code>)
value	object	--	Any JSON-serializable object, or <code>GlobalVarRawJson</code>
remark	string?	null	Optional remark or description

SaveGlobalVars(IReadOnlyCollection<GlobalVarSaveItem> items)

Parameter	Type	Default	Description
items	IReadOnlyCollection<GlobalVarSaveItem>	--	Collection of variables to save

Returns: `Task<CommonResponse>` — controller response

Throws: `CodroidCommandException` (controller error), `TimeoutException` (no response within 10s), `ArgumentException` (invalid variable name)


```
// Single
await robot.SaveGlobalVar("counter", 42, "test counter");

// Batch
await robot.SaveGlobalVars(new[]
{
    new GlobalVarSaveItem("x", 100.0, "X position"),
    new GlobalVarSaveItem("y", 200.0, "Y position"),
});
```

RemoveGlobalVars

```
public async Task<CommonResponse> RemoveGlobalVars(IEnumerable<string> names)
```

Deletes specified global variables. Deleting nonexistent variables is not an error.

Parameter	Type	Default	Description
names	<code>IEnumerable<string></code>	--	Variable names to delete

Returns: `Task<CommonResponse>` — controller response

Throws: `CodroidCommandException` (controller error), `TimeoutException` (no response within 10s)

```
await robot.RemoveGlobalVars(new[] { "counter", "x", "y" });
```

16. Kinematics

AposToCpos / AposToCposPose (Forward Kinematics)

```
public async Task<CommonResponse> AposToCpos(double[] jointDegrees, double[]
userFrame, double[] toolFrame, double[]? externalAxisPositions = null)
public async Task<double[]> AposToCposPose(double[] jointDegrees, double[] userFrame,
double[] toolFrame, double[]? externalAxisPositions = null)
```

Forward kinematics: joint space to Cartesian space. `AposToCposPose` returns [x,y,z,rx,ry,rz] in mm+deg.

Parameter	Type	Default	Description
<code>jointDegrees</code>	<code>double[]</code>	--	6 joint angles in degrees
<code>userFrame</code>	<code>double[]</code>	--	User coordinate frame [x,y,z,rx,ry,rz] (mm + deg)
<code>toolFrame</code>	<code>double[]</code>	--	Tool coordinate frame [x,y,z,rx,ry,rz] (mm + deg)
<code>externalAxisPositions</code>	<code>double[]?</code>	null	External axis positions

AposToCpos Returns: `Task<CommonResponse>` — controller response

AposToCposPose Returns: `Task<double[]>` — [x,y,z,rx,ry,rz] in mm + deg

Throws: `CodroidCommandException` (controller error), `TimeoutException` (no response within 10s)

```
double[] joints = { 0, 0, 90, 0, 90, 0 };
double[] userFrame = { 0, 0, 0, 0, 0, 0 };
double[] toolFrame = { 0, 0, 100, 0, 0, 0 };

double[] pose = await robot.AposToCposPose(joints, userFrame, toolFrame);
Console.WriteLine($"TCP: [{string.Join(", ", pose.Select(v => v.ToString("F1"))}]");
// TCP: [400.0, 0.0, 300.0, 180.0, 0.0, 0.0]
```

CposToApos / CposToAposJoints (Inverse Kinematics)

```
public async Task<CommonResponse> CposToApos(double[] cartesianMmDeg, double[]
referenceJointDegrees, double[]? externalAxisPositions = null)
public async Task<double[]> CposToAposJoints(double[] cartesianMmDeg, double[]
referenceJointDegrees, double[]? externalAxisPositions = null)
```

Inverse kinematics: Cartesian to joint space. `CposToAposJoints` returns 6 joint angles in degrees.

Parameter	Type	Default	Description
cartesianMmDeg	double[]	--	Cartesian pose [x,y,z,rx,ry,rz] in mm + deg
referenceJointDegrees	double[]	--	Reference joint angles (starting guess for IK solver)
externalAxisPositions	double[]?	null	External axis positions

CposToApos Returns: Task<CommonResponse> — controller response

CposToAposJoints Returns: Task<double[]> — 6 joint angles in degrees

Throws: CodroidCommandException (controller error), TimeoutException (no response within 10s), InvalidOperationException (no IK solution found)

```
double[] pose = { 400, 0, 300, 180, 0, 0 };
double[] refJoints = { 0, 0, 90, 0, 90, 0 };

double[] joints = await robot.CposToAposJoints(pose, refJoints);
Console.WriteLine($"Joints: [{string.Join(", ", joints.Select(v =>
v.ToString("F2")))]}");
```

CalculateRelativePose / CalculateRelativePoseResult

```
public async Task<CommonResponse> CalculateRelativePose(double[] tcpPoseWorld,
double[] offset, RelativePoseCoorType coorType, double[]? tcpPoseInPosCoorFrame =
null, double[]? userCoorFrame = null)
public async Task<double[]> CalculateRelativePoseResult(double[] tcpPoseWorld,
double[] offset, RelativePoseCoorType coorType, double[]? tcpPoseInPosCoorFrame =
null, double[]? userCoorFrame = null)
```

Calculates a relative pose / offset in user or tool coordinate frame.

Parameter	Type	Description
tcpPoseWorld	double[]	Current TCP pose in world frame

Parameter	Type	Description
offset	double[]	[dx,dy,dz,drx,dry,drz] offset
coordType	RelativePoseCoordType	User or Tool
tcpPoseInPosCoordFrame	double[]?	TCP pose in position coordinate frame
userCoordFrame	double[]?	User coordinate frame definition

CalculateRelativePose **Returns:** Task<CommonResponse> — controller response

CalculateRelativePoseResult **Returns:** Task<double[]> — [x,y,z,rx,ry,rz] relative pose in mm + deg

Throws: CodroidCommandException (controller error), TimeoutException (no response within 10s)

```
double[] currentPose = { 400, 0, 300, 180, 0, 0 };
double[] offset = { 50, 0, 0, 0, 0, 0 }; // Move +50mm in X

double[] newPose = await robot.CalculateRelativePoseResult(
    currentPose, offset, RelativePoseCoordType.User);

Console.WriteLine($"New pose: [{string.Join(", ", newPose)}]");
```

4. Motion API Reference

This section covers all motion-related types in the CodroidCS SDK, including joint/Cartesian point definitions, move instructions, jog parameters, and motion wait options.

Table of Contents

1. [JointPoint](#)
 2. [CartesianPoint](#)
 3. [MovePoint](#)
 4. [MoveInstruction](#)
 5. [MoveToTarget](#)
 6. [MoveToKind](#)
 7. [MoveKinds](#)
 8. [MotionWaitOptions](#)
 9. [RobotJogParameters](#)
 10. [RobotJogMode](#)
 11. [RobotJogFrameType](#)
-

1. JointPoint

A sealed class representing a robot target defined by joint angles.

`JointPoint` stores 6 joint angles in degrees and is used when you want to move the robot to an exact joint configuration without ambiguity.

Properties

Property	Type	Description
Jp	double[]	6 joint angles in degrees

Factory Methods

Method	Description
JointPoint.Degrees(double[] jointsDeg)	Create from 6 joint angles in degrees. The array must be exactly length 6.

Example

```
// Create a joint point with all 6 joint angles in degrees
var jp = JointPoint.Degrees(new[] { 0, 0, 90, 0, 90, 0 });

// Use in a move instruction
await robot.Move(MoveInstruction.MovJ(jp, speed: 40, acc: 100));
```

2. CartesianPoint

A sealed class representing a robot target defined by Cartesian (TCP) pose, with optional reference joints for inverse kinematics.

`CartesianPoint` stores a TCP pose as `[x, y, z, rx, ry, rz]` in millimeters and degrees. When only a pose is provided, the controller uses default reference joints `[20, 20, 20, 20, 20, 20]` for inverse kinematics. You can supply explicit reference joints to guide the IK solver toward a specific configuration.

Properties

Property	Type	Description
Cp	double[]	TCP pose <code>[x, y, z, rx, ry, rz]</code> -- position in mm, orientation in degrees

Property	Type	Description
Rj	double[]?	Reference joints for IK (6 joint angles in degrees). <code>null</code> uses default [20,20,20,20,20,20]

Factory Methods

Method	Description
<code>CartesianPoint.MmDeg(double[] poseMmDeg)</code>	Create with TCP pose only (uses default reference joints)
<code>CartesianPoint.MmDegWithRef(double[] poseMmDeg, double[] refJointsDeg)</code>	Create with TCP pose and explicit reference joints for IK

Examples

```
// Create a Cartesian point with TCP pose only (position + orientation)
var cp = CartesianPoint.MmDeg(new[] { 400, 0, 300, 180, 0, 0 });

// Create a Cartesian point with explicit reference joints from current robot state
var refJ = robot.CriData.JointPosition;
var cpWithRef = CartesianPoint.MmDegWithRef(
    new[] { 400, 0, 300, 180, 0, 0 },
    refJ
);

// Use in a linear move instruction
await robot.Move(MoveInstruction.MovL(cp, speed: 150, acc: 500));
```

3. MovePoint

A sealed class used internally for serialization of move target points.

`MovePoint` is the serialization wrapper used when sending move instructions to the controller. It holds the optional joint (`Jp`), Cartesian (`Cp`), reference joint (`Rj`), and external (`Ep`) arrays. You typically do not create `MovePoint` instances directly; use the factory methods on `MoveInstruction` instead.

Properties

Property	Type	Description
Jp	double[]?	Joint angles (degrees), null if Cartesian target
Cp	double[]?	TCP pose (mm + deg), null if joint target
Rj	double[]?	Reference joints for IK
Ep	double[]?	External axes

All properties use `[JsonIgnoreWhenNull]` -- they are omitted from JSON serialization when null.

Factory Methods

Method	Description
<code>MovePoint.FromJoint(JointPoint jp)</code>	Create from a <code>JointPoint</code>
<code>MovePoint.FromCartesian(CartesianPoint cp)</code>	Create from a <code>CartesianPoint</code>

Example

```
// Typically you do not create MovePoint directly. Use MoveInstruction factories.
```

```
// If you need to wrap a point explicitly:
```

```
var jp = JointPoint.Degrees(new[] { 0, 0, 90, 0, 90, 0 });
var movePoint = MovePoint.FromJoint(jp);
```

```
var cp = CartesianPoint.MmDeg(new[] { 400, 0, 300, 180, 0, 0 });
var movePointFromCart = MovePoint.FromCartesian(cp);
```

4. MoveInstruction

A sealed class that defines a single motion segment in a robot move command.

`MoveInstruction` is the primary type for building motion paths. Each instance describes one segment with a motion type (joint, linear, or circular), speed/acceleration parameters, blending settings, and optional coordinate system and tool offsets.

Properties

Property	Type	Default	Description
Type	string	"movJ"	Motion type: "movJ" , "movL" , "movC" , "movCircle"
CircleNum	int?	null	Number of full circles (only for <code>movCircle</code>)
Speed	double	--	Speed value (mm/s for linear, deg/s for joint)
Acc	double	--	Acceleration value
Blend	double?	null	Blend radius (mm for linear, deg for joint). Mutually exclusive with <code>RelativeBlend</code> . Omit for no transition
RelativeBlend	double?	null	Relative blend ratio (0-100). Mutually exclusive with <code>Blend</code> — if both set, this is ignored
TargetPoint	MovePoint	--	The target point for this segment
MiddlePoint	MovePoint?	null	Middle/via point (required for <code>movC</code> and <code>movCircle</code>)
Coor	double[]?	null	Coordinate system definition
Tool	double[]?	null	Tool definition

Factory Methods

All factories share common optional parameters: `coor` (coordinate system), `tool` (tool offset), and `relativeBlend` (relative blend ratio).

Method	Motion Type	Target Types	Description
<code>MoveInstruction.MovJ(JointPoint, speed, acc, blend, ...)</code>	Joint	JointPoint	Joint move to joint target
<code>MoveInstruction.MovJ(CartesianPoint, speed, acc, blend, ...)</code>	Joint	CartesianPoint	Joint move to Cartesian target

Method	Motion Type	Target Types	Description
<code>MoveInstruction.MovL(CartesianPoint, speed, acc, blend, ...)</code>	Linear	CartesianPoint	Linear move to Cartesian target
<code>MoveInstruction.MovL(JointPoint, speed, acc, blend, ...)</code>	Linear	JointPoint	Linear move to joint target
<code>MoveInstruction.MovC(CartesianPoint middle, CartesianPoint target, speed, acc, blend, ...)</code>	Circular	2x CartesianPoint	Circular arc through middle to target
<code>MoveInstruction.MovCircle(CartesianPoint middle, CartesianPoint target, int circleNum, speed, acc, blend, ...)</code>	Full Circle	2x CartesianPoint + circleNum	Full circle motion

Parameter Reference

Parameter	Type	Default	Description
<code>speed</code>	<code>double</code>	<code>--</code>	Required. Speed (mm/s or deg/s)
<code>acc</code>	<code>double</code>	<code>--</code>	Required. Acceleration
<code>blend</code>	<code>double?</code>	<code>null</code>	Blend radius. Mutually exclusive with <code>relativeBlend</code> — if both set, <code>relativeBlend</code> is ignored. Omit for no transition
<code>coor</code>	<code>double[]?</code>	<code>null</code>	User coordinate frame. <code>null</code> = omitted from command
<code>tool</code>	<code>double[]?</code>	<code>null</code>	Tool coordinate frame. <code>null</code> = omitted from command
<code>relativeBlend</code>	<code>double?</code>	<code>null</code>	Relative blend (0-100). Mutually exclusive with <code>blend</code> — if both set, this is ignored

Examples

```
// Single joint move to a joint target
var j1 = JointPoint.Degrees(new[] { 20, 20, 90, 0, 45, 0 });
await robot.Move(MoveInstruction.MovJ(j1, speed: 40, acc: 100));
```

```

// Single linear move to a Cartesian target
var cp = CartesianPoint.MmDeg(new[] { 400, 0, 300, 180, 0, 0 });
await robot.Move(MoveInstruction.MovL(cp, speed: 150, acc: 500));

// Multi-segment path: joint move followed by linear move
var p2 = new[] { 500, 100, 400, 180, 0, 0 };
var refJ = robot.CriData.JointPosition;
await robot.Move(new[]
{
    MoveInstruction.MovJ(JointPoint.Degrees(j1), 40, 100),
    MoveInstruction.MovL(CartesianPoint.MmDegWithRef(p2, refJ), 150, 500),
});

// Circular arc motion
var mid = CartesianPoint.MmDeg(new[] { 450, 50, 350, 180, 0, 0 });
var end = CartesianPoint.MmDeg(new[] { 500, 0, 300, 180, 0, 0 });
await robot.Move(MoveInstruction.MovC(mid, end, speed: 100, acc: 300));

// Full circle motion (2 full rotations)
await robot.Move(MoveInstruction.MovCircle(mid, end, circleNum: 2, speed: 80, acc:
200));

// With custom blend and coordinate system
await robot.Move(MoveInstruction.MovL(cp, speed: 100, acc: 300, blend: 10, coor:
userCoord));

```

5. MoveToTarget

A sealed class representing a target for pre-defined move-to commands (home, safe, pack, etc.).

`MoveToTarget` wraps a target point for use with `MoveToKind` commands. It can represent a joint target, a Cartesian target, or raw external axis data.

Properties

Property	Type	Description
Cp	double[]?	Cartesian pose [x, y, z, rx, ry, rz] (mm + deg)
Jp	double[]?	Joint angles (degrees)
Ep	double[]?	External axes

Factory Methods

Method	Description
MoveToTarget.Joint(JointPoint jp)	Create from a JointPoint
MoveToTarget.Cartesian(CartesianPoint cp)	Create from a CartesianPoint

Example

```
// Create a moveTo target from a joint point
var homeTarget = MoveToTarget.Joint(JointPoint.Degrees(new[] { 0, 0, 0, 0, 0, 0 }));

// Create a moveTo target from a Cartesian point
var safeTarget = MoveToTarget.Cartesian(
    CartesianPoint.MmDeg(new[] { 300, 0, 400, 180, 0, 0 })
);
```

6. MoveToKind

An enum specifying pre-defined move-to target types.

`MoveToKind` is used with the robot's `MoveTo` method to command the robot to move to well-known positions or resume program execution.

Values

Name	Value	Description
Stop	-1	Stop the moveTo operation
Home	0	Home position
Safe	1	Safe position
Candle	2	Candle (vertical) position
Pack	3	Pack (transport) position
JointPlanned	4	Joint planned move to target
LinePlanned	5	Linear planned move to target
ProgramResume	6	Resume program execution

Example

```
// Move the robot to the home position
await robot.MoveTo(MoveToKind.Home);

// Stop an in-progress moveTo operation
await robot.MoveTo(MoveToKind.Stop);

// Move to a specific joint position with joint planning
var target = MoveToTarget.Joint(JointPoint.Degrees(new[] { 10, 20, 90, 0, 45, 0 }));
await robot.MoveTo(MoveToKind.JointPlanned, target);

// Move to a Cartesian position with linear planning
var cartTarget = MoveToTarget.Cartesian(
    CartesianPoint.MmDeg(new[] { 400, 0, 300, 180, 0, 0 })
);
await robot.MoveTo(MoveToKind.LinePlanned, cartTarget);

// Resume a paused program
await robot.MoveTo(MoveToKind.ProgramResume);
```

7. MoveKinds

A static class providing string constants for motion type identifiers.

`MoveKinds` defines the string constants used in `MoveInstruction.Type`. These correspond to the four supported motion modes in the CodroidCS controller.

Constants

Name	Value	Description
<code>MovJ</code>	<code>"movJ"</code>	Joint move
<code>MovL</code>	<code>"movL"</code>	Linear move
<code>MovC</code>	<code>"movC"</code>	Circular arc move
<code>MovCircle</code>	<code>"movCircle"</code>	Full circle move

Example

```
// Compare the motion type of an instruction
var instruction = MoveInstruction.MovJ(
    JointPoint.Degrees(new[] { 0, 0, 90, 0, 90, 0 }),
    speed: 40, acc: 100
);

if (instruction.Type == MoveKinds.MovJ)
{
    Console.WriteLine("This is a joint move.");
}
else if (instruction.Type == MoveKinds.MovL)
{
    Console.WriteLine("This is a linear move.");
}
```

8. MotionWaitOptions

A sealed class that configures how the SDK waits for motion completion.

`MotionWaitOptions` controls the polling behavior, tolerance thresholds, and timeout when waiting for a robot motion to complete. You can customize these parameters to suit different precision and responsiveness requirements.

Properties

Property	Type	Default	Description
<code>Timeout</code>	<code>TimeSpan</code>	60 seconds	Maximum time to wait for motion completion
<code>PollInterval</code>	<code>TimeSpan</code>	50 ms	Interval between each poll to check motion status
<code>CriStaleTimeout</code>	<code>TimeSpan</code>	500 ms	Maximum age of CRI data before considered stale
<code>SettledSamples</code>	<code>int</code>	3	Number of consecutive settled samples required to confirm motion is complete
<code>JointToleranceDeg</code>	<code>double</code>	0.2	Joint position tolerance in degrees
<code>CartesianPositionToleranceMm</code>	<code>double</code>	1.0	Cartesian position tolerance in millimeters
<code>CartesianOrientationToleranceDeg</code>	<code>double</code>	1.0	Cartesian orientation tolerance in degrees

Example

```
// Use default wait options (most common)
await robot.Move(MoveInstruction.MovJ(jp, speed: 40, acc: 100));

// Customize wait options for high-precision motion
var preciseWait = new MotionWaitOptions
{
    Timeout = TimeSpan.FromSeconds(120),
```

```

        PollInterval = TimeSpan.FromMilliseconds(20),
        SettledSamples = 5,
        JointToleranceDeg = 0.05,
        CartesianPositionToleranceMm = 0.2,
        CartesianOrientationToleranceDeg = 0.5,
    };

    await robot.Move(MoveInstruction.MovL(cp, speed: 50, acc: 200), preciseWait);

    // Use a short timeout for quick motions
    var quickWait = new MotionWaitOptions
    {
        Timeout = TimeSpan.FromSeconds(10),
        PollInterval = TimeSpan.FromMilliseconds(30),
    };

    await robot.Move(MoveInstruction.MovJ(jp, speed: 100, acc: 300), quickWait);

    // Fire-and-forget: set a very long timeout to effectively not wait
    var longWait = new MotionWaitOptions
    {
        Timeout = TimeSpan.FromHours(1),
    };

```

9. RobotJogParameters

A sealed class defining parameters for robot jog (manual) movements.

`RobotJogParameters` specifies the jog mode (joint or linear), speed, axis index, and coordinate frame for manual robot jogging operations.

Properties

Property	Type	Description
Mode	RobotJogMode	Jog mode: Joint or Linear
Speed	double	Jog speed (deg/s for joint, mm/s for linear)

Property	Type	Description
Index	int	Axis index (0-5 for joint mode)
CoorType	RobotJogFrameType	Coordinate frame type: User or Tool
CoorId	int	Coordinate frame ID

Factory Method

Method	Description
<code>RobotJogParameters.Create(RobotJogMode mode, double speed, int index, RobotJogFrameType frame, int coorId)</code>	Create jog parameters

Example

```
// Jog joint 0 at 20 deg/s in user coordinate frame 0
var jogParams = RobotJogParameters.Create(
    mode: RobotJogMode.Joint,
    speed: 20,
    index: 0,
    frame: RobotJogFrameType.User,
    coorId: 0
);
await robot.Jog(jogParams);

// Jog linear along X axis at 50 mm/s in tool coordinate frame 1
var linearJog = RobotJogParameters.Create(
    mode: RobotJogMode.Linear,
    speed: 50,
    index: 0, // X axis
    frame: RobotJogFrameType.Tool,
    coorId: 1
);
await robot.Jog(linearJog);
```

10. RobotJogMode

An enum specifying the jog motion mode.

Values

Name	Value	Description
Joint	1	Jog individual joints
Linear	2	Jog linearly in Cartesian space

Example

```
// Switch between joint and linear jog modes
if (jogMode == RobotJogMode.Joint)
{
    Console.WriteLine("Joint jog mode - move individual joints.");
}
else if (jogMode == RobotJogMode.Linear)
{
    Console.WriteLine("Linear jog mode - move in Cartesian space.");
}
```

11. RobotJogFrameType

An enum specifying the coordinate frame type for jog operations.

Values

Name	Value	Description
User	0	User-defined coordinate frame
Tool	1	Tool coordinate frame

Example

```
// Choose coordinate frame for jog operation
var jogParams = RobotJogParameters.Create(
    mode: RobotJogMode.Linear,
    speed: 30,
    index: 1, // Y axis
    frame: RobotJogFrameType.User, // Use user frame
    coordId: 0
);
await robot.Jog(jogParams);
```

Complete Multi-Segment Path Example

The following example demonstrates building a complete motion program using multiple types from this API reference.

```
using CodroidCS.Sdk;

// 1. Define waypoints
var homeJoint = JointPoint.Degrees(new[] { 0, 0, 90, 0, 90, 0 });
var pickJoint = JointPoint.Degrees(new[] { 30, -20, 80, 10, 60, -5 });

var refJ = robot.CriData.JointPosition;
var pickCart = CartesianPoint.MmDegWithRef(
    new[] { 450, -100, 200, 180, 0, 0 },
    refJ
);
var placeCart = CartesianPoint.MmDeg(
    new[] { 450, 100, 200, 180, 0, 0 }
);
var viaPoint = CartesianPoint.MmDeg(
    new[] { 475, 0, 250, 180, 0, 0 }
);

// 2. Build a multi-segment path
```

```

var path = new[]
{
    // Move to home with joint motion
    MoveInstruction.MovJ(homeJoint, speed: 60, acc: 120),

    // Move to pick position with joint motion
    MoveInstruction.MovJ(pickJoint, speed: 40, acc: 100),

    // Linear approach to pick Cartesian point
    MoveInstruction.MovL(pickCart, speed: 80, acc: 300, blend: 5),

    // Arc motion from pick to place via waypoint
    MoveInstruction.MovC(viaPoint, placeCart, speed: 100, acc: 300),

    // Return home with linear motion
    MoveInstruction.MovL(
        CartesianPoint.MmDeg(new[] { 300, 0, 400, 180, 0, 0 }),
        speed: 150, acc: 500
    ),
};

// 3. Execute with custom wait options
var waitOptions = new MotionWaitOptions
{
    Timeout = TimeSpan.FromSeconds(90),
    SettledSamples = 4,
    JointToleranceDeg = 0.1,
};

await robot.Move(path, waitOptions);

// 4. Verify completion
Console.WriteLine("Path execution complete.");

```

5. Data Types and Enums

This section provides a comprehensive reference for all data types, enums, and exceptions in the Codroid CRI SDK.

Table of Contents

1. [CommonResponse](#)
 2. [CriRealTimeData](#)
 3. [RobotFrame](#)
 4. [RobotPayloadFrame](#)
 5. [RobotParameters](#)
 6. [RegisterReadValue](#)
 7. [RegisterExtendArrayValueType](#)
 8. [IoPortKind](#)
 9. [RelativePoseCoorType](#)
 10. [CodroidCommandException](#)
 11. [GlobalVarSaveItem](#)
 12. [GlobalVarRawJson](#)
 13. [GlobalVarCatalogEntry](#)
-

1. CommonResponse

A general-purpose response class returned by most CRI SDK methods. Contains the request ID, a type identifier, a JSON data payload, and an optional error message.

Properties

Property	Type	Description
id	object?	The request identifier
ty	string?	The response type identifier
db	JsonElement	The response data payload
err	string?	Error message, if any

Example: Reading the db field

```
CommonResponse response = await client.SomeMethodAsync();
```

```
// Check for errors first
```

```
if (response.err != null)
```

```
{
```

```
    Console.WriteLine($"Error: {response.err}");
```

```
    return;
```

```
}
```

```
// Read db as a specific type
```

```
int value = response.db.GetInt32();
```

```
Console.WriteLine($"Value: {value}");
```

```
// Or read as JSON string
```

```
string json = response.db.GetRawText();
```

```
Console.WriteLine($"Raw JSON: {json}");
```

2. CriRealTimeData

Contains all real-time data fields from the robot controller, including joint positions, TCP poses, status flags, and more. Updated continuously via the CRI connection.

Properties

Timestamp

Property	Type	Description
TimestampMs	long	Timestamp in milliseconds

Status Flags

Property	Type	Description
Status1Raw	ushort	Raw status word 1
Status2Raw	ushort	Raw status word 2
ProjectRunning	bool	Whether a project is currently running
ProjectStopped	bool	Whether the project is stopped
ProjectPaused	bool	Whether the project is paused
Enabling	bool	Whether the enabling switch is active
NotEnabled	bool	Whether the robot is not enabled
ManualMode	bool	Whether in manual mode
Dragging	bool	Whether the robot is being dragged
InMotion	bool	Whether the robot is in motion
CollisionStopped	bool	Whether stopped due to collision
InSafetyPosition	bool	Whether in the safety position
HasAlarm	bool	Whether an alarm is active
SimulationMode	bool	Whether in simulation mode
EmergencyStopPressed	bool	Whether the E-stop is pressed
RescueMode	bool	Whether in rescue mode
AutoMode	bool	Whether in auto mode
RemoteMode	bool	Whether in remote mode
RealTimeControlMode	bool	Whether in real-time control mode

Property	Type	Description
CriErrorCode	byte	CRI error code

Joint Data

Property	Type	Description
JointPosition	double[6]	Joint positions in degrees
JointVelocity	double[6]	Joint velocities
JointOutputTorque	double[6]	Joint output torques
JointExternalForce	double[6]	Joint external forces

TCP Data

Property	Type	Description
TcpPose	double[6]	TCP pose (mm + deg)
TcpVelocity	double[6]	TCP velocity
TcpLinearVelocity	double	TCP linear velocity magnitude

External

Property	Type	Description
ExternalAxisPosition	double[]	External axis positions

Methods

Method	Return Type	Description
UpdateFrom(CriRealTimeData)	void	Copies all fields from another instance
Clone()	CriRealTimeData	Creates a deep copy

Example: Subscribing to CRI data

```
// Subscribe to real-time data
client.OnCriDataReceived += (sender, data) =>
{
    // Read timestamp
    long timestamp = data.TimestampMs;

    // Read joint positions (in degrees)
    double joint1 = data.JointPosition[0];
    double joint2 = data.JointPosition[1];
    double joint3 = data.JointPosition[2];

    Console.WriteLine($"J1={joint1:F2}, J2={joint2:F2}, J3={joint3:F2}");

    // Read TCP pose
    double tcpX = data.TcpPose[0]; // mm
    double tcpY = data.TcpPose[1]; // mm
    double tcpZ = data.TcpPose[2]; // mm

    Console.WriteLine($"TCP X={tcpX:F2} Y={tcpY:F2} Z={tcpZ:F2}");

    // Check status
    if (data.HasAlarm)
    {
        Console.WriteLine("Robot has an alarm!");
    }
};

// Or clone for thread-safe access
CriRealTimeData snapshot = data.Clone();
```

3. RobotFrame

A sealed class representing a coordinate frame definition, used for both tool frames and user coordinate frames. Contains an ID and a 6-axis pose (position + orientation).

Properties

Property	Type	Description
Id	int	Frame identifier
X	double	X position (mm)
Y	double	Y position (mm)
Z	double	Z position (mm)
A	double	Rotation around X axis (deg)
B	double	Rotation around Y axis (deg)
C	double	Rotation around Z axis (deg)

Example

```
// Access a tool frame
RobotFrame tool = robotParams.Tool[0];
Console.WriteLine($"Tool {tool.Id}: X={tool.X}, Y={tool.Y}, Z={tool.Z}");
Console.WriteLine($"  A={tool.A}, B={tool.B}, C={tool.C}");
```

4. RobotPayloadFrame

A sealed class representing a payload definition, including mass and center of mass coordinates.

Properties

Property	Type	Description
Id	int	Payload identifier
M	double	Mass (kg)
Mx	double	Center of mass X (mm)
My	double	Center of mass Y (mm)
Mz	double	Center of mass Z (mm)

Example

```
// Access a payload configuration
RobotPayloadFrame payload = robotParams.Payload[0];
Console.WriteLine($"Payload {payload.Id}: Mass={payload.M}kg");
Console.WriteLine($"  CoM: ({payload.Mx}, {payload.My}, {payload.Mz})");
```

5. RobotParameters

A sealed class containing the complete set of robot parameters, including default IDs for tool, payload, and coordinate frames, as well as the full lists of configured frames.

Properties

Property	Type	Description
DefaultToolId	int	Default tool frame ID
DefaultPayloadId	int	Default payload ID
DefaultCoordinateId	int	Default coordinate frame ID
MaxPayload	double	Maximum payload (kg)
Tool	List<RobotFrame>	Tool frames list
Payload	List<RobotPayloadFrame>	Payload configurations list
Coordinate	List<RobotFrame>	User coordinate frames list

Example: Reading robot parameters

```
RobotParameters parameters = await client.GetRobotParametersAsync();

// Read defaults
Console.WriteLine($"Default Tool ID: {parameters.DefaultToolId}");
Console.WriteLine($"Default Payload ID: {parameters.DefaultPayloadId}");
Console.WriteLine($"Default Coordinate ID: {parameters.DefaultCoordinateId}");
Console.WriteLine($"Max Payload: {parameters.MaxPayload} kg");
```

```
// Iterate tool frames
Console.WriteLine("Tool Frames:");
foreach (RobotFrame tool in parameters.Tool)
{
    Console.WriteLine($" [{tool.Id}] X={tool.X}, Y={tool.Y}, Z={tool.Z}, "
        + $"A={tool.A}, B={tool.B}, C={tool.C}");
}

// Iterate payloads
Console.WriteLine("Payloads:");
foreach (RobotPayloadFrame payload in parameters.Payload)
{
    Console.WriteLine($" [{payload.Id}] M={payload.M}kg, "
        + $"CoM=({payload.Mx}, {payload.My}, {payload.Mz})");
}

// Iterate coordinate frames
Console.WriteLine("Coordinate Frames:");
foreach (RobotFrame coord in parameters.Coordinate)
{
    Console.WriteLine($" [{coord.Id}] X={coord.X}, Y={coord.Y}, Z={coord.Z}, "
        + $"A={coord.A}, B={coord.B}, C={coord.C}");
}
```

6. RegisterReadValue

A readonly struct representing a value read from a controller register, with helpers to convert the value to common types.

Properties

Property	Type	Description
Address	int	Register address
Value	JsonElement	Raw value as JSON

Methods

Method	Return Type	Description
<code>GetInt32()</code>	<code>int</code>	Converts value to Int32
<code>GetDouble()</code>	<code>double</code>	Converts value to Double
<code>TryGetInt32(out int)</code>	<code>bool</code>	Safely tries to convert to Int32

Example: Reading and converting register values

```
// Read registers
List<RegisterReadValue> values = await client.ReadRegistersAsync(address: 0, count: 5);

foreach (RegisterReadValue reg in values)
{
    Console.WriteLine($"Register [{reg.Address}] raw: {reg.Value}");

    // Direct conversion (throws on failure)
    int intVal = reg.GetInt32();
    Console.WriteLine($"  As Int32: {intVal}");

    // Safe conversion
    if (reg.TryGetInt32(out int safeVal))
    {
        Console.WriteLine($"  Safe Int32: {safeVal}");
    }
    else
    {
        Console.WriteLine("  Cannot convert to Int32");
    }

    // As double
    double dblVal = reg.GetDouble();
    Console.WriteLine($"  As Double: {dblVal}");
}
```

7. RegisterExtendArrayValueType

A static class defining constants for the data types used in extended register arrays.

Constants

Constant	Value	Description
Bool	0	Boolean type
UInt8	1	Unsigned 8-bit integer
Int8	2	Signed 8-bit integer
UInt16	3	Unsigned 16-bit integer
Int16	4	Signed 16-bit integer
UInt32	5	Unsigned 32-bit integer
Int32	6	Signed 32-bit integer
Float32	7	32-bit floating point

Example

```
// Specify value type when writing extended registers
await client.WriteExtendRegisterAsync(
    address: 0,
    values: new[] { 3.14f },
    valueType: RegisterExtendArrayValueType.Float32
);
```

8. IoPortKind

A static class defining constants for the different kinds of I/O ports available on the controller.

Constants

Constant	Value	Description
Di	"DI"	Digital Input
Do	"DO"	Digital Output
Ai	"AI"	Analog Input
Ao	"AO"	Analog Output

Example

```
// Read a digital input
bool diValue = await client.ReadDigitalInputAsync(port: IoPortKind.Di, address: 0);

// Write a digital output
await client.WriteDigitalOutputAsync(port: IoPortKind.Do, address: 0, value: true);

// Read an analog input
double aiValue = await client.ReadAnalogInputAsync(port: IoPortKind.Ai, address: 0);
```

9. RelativePoseCoorType

An enum specifying the coordinate system in which a relative pose is expressed.

Values

Name	Value	Description
User	0	User (world) coordinate system
Tool	1	Tool coordinate system

Example


```
// Move relative in tool coordinate system
await client.MoveRelativeAsync(
    pose: new[] { 0, 0, 10, 0, 0, 0 }, // Move 10mm in Z
    coordType: RelativePoseCoordType.Tool
);

// Move relative in user coordinate system
await client.MoveRelativeAsync(
    pose: new[] { 10, 0, 0, 0, 0, 0 }, // Move 10mm in X
    coordType: RelativePoseCoordType.User
);
```

10. CodroidCommandException

A sealed exception class thrown when a CRI command fails. Provides detailed context about the failure including the request ID, command type, controller error message, and the full response.

Inheritance



Properties

Property	Type	Description
RequestId	int	The ID of the failed request
CommandType	string	The type of command that failed
ControllerError	string?	Error from the controller
Response	CommonResponse?	The full response object

Constructor

```
public CodroidCommandException(  
    int requestId,  
    string commandType,  
    string? controllerError,  
    CommonResponse? response  
)
```

Example: Catching and inspecting

```
try  
{  
    await client.MoveJointAsync(target: new[] { 0, 0, 90, 0, 90, 0 });  
}  
catch (CodroidCommandException ex)  
{  
    Console.WriteLine("Command failed!");  
    Console.WriteLine($" Request ID: {ex.RequestId}");  
    Console.WriteLine($" Command Type: {ex.CommandType}");  
    Console.WriteLine($" Controller Error: {ex.ControllerError}");  
  
    if (ex.Response != null)  
    {  
        Console.WriteLine($" Response error: {ex.Response.err}");  
        Console.WriteLine($" Response data: {ex.Response.db.GetRawText()}");  
    }  
  
    // Re-throw or handle  
    throw;  
}
```

11. GlobalVarSaveItem

A readonly record struct used to specify a global variable to be saved or written to the controller, including its name, value, and an optional remark.

Constructor

```
public GlobalVarSaveItem(string Name, object Value, string? Remark = null)
```

Parameter	Type	Required	Description
Name	string	Yes	Variable name
Value	object	Yes	Variable value
Remark	string?	No (default: null)	Optional remark

Example

```
// Create items to save
var items = new List<GlobalVarSaveItem>
{
    new GlobalVarSaveItem("Counter", 42, "Production count"),
    new GlobalVarSaveItem("Speed", 50.5, "Motion speed"),
    new GlobalVarSaveItem("Flag", true)
};

await client.SaveGlobalVarsAsync(items);
```

12. GlobalVarRawJson

A readonly record struct that wraps a raw JSON string literal for writing global variables with complex or custom JSON structures.

Constructor

```
public GlobalVarRawJson(string Literal)
```

Parameter	Type	Required	Description
Literal	string	Yes	Raw JSON string

Example

```
// Write a complex variable using raw JSON
var rawJson = new GlobalVarRawJson(
    """
    {"positions": [1.0, 2.0, 3.0], "enabled": true}
    """
);

await client.WriteGlobalVarRawAsync("MyConfig", rawJson);
```

13. GlobalVarCatalogEntry

A sealed class representing a single entry in the global variable catalog, containing the variable's current value and optional remark.

Properties

Property	Type	Default	Description
Value	JsonElement	--	The variable's current value
Remark	string	""	Remark or description

Example

```
// Read the global variable catalog
Dictionary<string, GlobalVarCatalogEntry> catalog =
    await client.GetGlobalVarCatalogAsync();

foreach (var (name, entry) in catalog)
{
    Console.WriteLine($"Variable: {name}");
    Console.WriteLine($"    Value: {entry.Value.GetRawText()}");
    Console.WriteLine($"    Remark: {entry.Remark}");
}
```

6. CRI Real-Time Data and Control API Reference

This section covers the CRI (Codroid Real-time Interface) APIs for real-time robot control, trajectory generation, and data parsing.

Table of Contents

- 1. [CriRealtimeDispatcher](#)
- 2. [TrajectoryGenerator](#)
- 3. [TrajectoryRequest](#)
- 4. [TrajectoryPoint](#)
- 5. [TrajectorySpace](#)
- 6. [TrajectoryProfile](#)
- 7. [CriRealtimePacketParser](#)
- 8. [Complete CRI Control Flow Example](#)

1. CriRealtimeDispatcher

Sealed class, implements IDisposable

A UDP-based command dispatcher that sends real-time motion commands to the robot controller. Supports single-frame commands and full trajectory playback with configurable SI-unit conversion.

Constants

Constant	Type	Value	Description
DefaultControllerUdpPort	int	9030	Default UDP port for CRI commands
CommandPacketLength	int	64	Fixed length of each command packet

Constructor

```
CriRealtimeDispatcher(string controllerIp, int controllerUdpPort = 9030, bool
convertToSi = true)
```

Parameter	Type	Default	Description
controllerIp	string	(required)	IP address of the robot controller
controllerUdpPort	int	9030	UDP port for sending commands
convertToSi	bool	true	If true , converts deg to rad and mm to m before sending. Matches CRI data stream units.

Methods

SendCommand

```
Task SendCommand(
    IReadOnlyList<double> position6,
    TrajectorySpace space,
    CancellationToken ct = default
)
```

Sends a single-frame position command to the controller. The `position6` list must contain exactly 6 elements (joint angles or Cartesian pose, depending on `space`).

Parameter	Type	Description
position6	IReadOnlyList<double>	Target position with exactly 6 elements
space	TrajectorySpace	Coordinate space: Joint or Cartesian
ct	CancellationToken	Cancellation token

Example:

```
// Send a single joint position command (degrees)
var dispatcher = new CriRealtimeDispatcher("192.168.8.136");
await dispatcher.SendCommand(
    new double[] { 0, 0, 90, 0, 90, 0 },
    TrajectorySpace.Joint
);
```

SendTrajectory

```
Task SendTrajectory(
    IEnumerable<TrajectoryPoint> trajectory,
    TrajectorySpace space,
    int periodMs,
    CancellationToken ct = default
)
```

Sends a complete trajectory to the controller at a fixed time interval. Each point is dispatched according to `periodMs` to maintain real-time timing.

Parameter	Type	Description
trajectory	IEnumerable<TrajectoryPoint>	Sequence of trajectory points to send
space	TrajectorySpace	Coordinate space: Joint or Cartesian
periodMs	int	Interval between points in milliseconds
ct	CancellationToken	Cancellation token

Example:

```
// Send trajectory at 4ms intervals (250Hz)
using var dispatcher = new CriRealtimeDispatcher("192.168.8.136");
await dispatcher.SendTrajectory(trajectory, TrajectorySpace.Joint, periodMs: 4);
```

Dispose

```
void Dispose()
```

Closes the underlying UDP socket and releases resources. Call this when you are done sending commands, or use a `using` statement to ensure automatic cleanup.

2. TrajectoryGenerator

Static class

Generates smooth trajectories between two positions using configurable motion profiles (cubic or trapezoidal). Returns an enumerable sequence of `TrajectoryPoint` objects.

Methods

Generate

```
static IEnumerable<TrajectoryPoint> Generate(
    IReadOnlyList<double> start,
    IReadOnlyList<double> target,
    TrajectoryRequest request
)
```

Generates a trajectory from `start` to `target` according to the parameters in `request`.

Parameter	Type	Description
<code>start</code>	<code>IReadOnlyList<double></code>	Starting position (joint angles or Cartesian)
<code>target</code>	<code>IReadOnlyList<double></code>	Target position (joint angles or Cartesian)
<code>request</code>	<code>TrajectoryRequest</code>	Trajectory generation parameters

Returns: `IEnumerable<TrajectoryPoint>` -- sequence of trajectory points

Example:


```

var start = new double[] { 0, 0, 90, 0, 90, 0 };
var target = new double[] { 10, 20, 45, 0, 60, 30 };

var request = new TrajectoryRequest
{
    Space = TrajectorySpace.Joint,
    Profile = TrajectoryProfile.Cubic,
    FrequencyHz = 250,
    Speed = 30
};

var trajectory = TrajectoryGenerator.Generate(start, target, request).ToList();
Console.WriteLine($"Generated {trajectory.Count} trajectory points");

```

3. TrajectoryRequest

Sealed class

Parameters that control how a trajectory is generated, including coordinate space, timing, speed, and motion profile.

Properties

Property	Type	Default	Description
Space	TrajectorySpace	(none)	Coordinate space for the trajectory
FrequencyHz	double	250.0	Sampling frequency in Hz
Speed	double?	null	Target speed (mutually exclusive with DurationSeconds)
DurationSeconds	double?	null	Total duration in seconds (mutually exclusive with Speed)
Profile	TrajectoryProfile	Cubic	Motion profile type
Acceleration	double	1000.0	Acceleration value for trapezoidal profile

Note: `Speed` and `DurationSeconds` are mutually exclusive. Set only one of them. If both are set, behavior is undefined.

Example:

```
// Using Speed
var requestBySpeed = new TrajectoryRequest
{
    Space = TrajectorySpace.Joint,
    FrequencyHz = 250,
    Speed = 30,
    Profile = TrajectoryProfile.Trapezoidal,
    Acceleration = 800
};

// Using DurationSeconds
var requestByDuration = new TrajectoryRequest
{
    Space = TrajectorySpace.Joint,
    FrequencyHz = 250,
    DurationSeconds = 2.5,
    Profile = TrajectoryProfile.Cubic
};
```

4. TrajectoryPoint

Sealed class

Represents a single point in a trajectory, containing a timestamp and a position array.

Properties

Property	Type	Default	Description
<code>TimeSeconds</code>	<code>double</code>	<code>0.0</code>	Time offset from trajectory start in seconds
<code>Position</code>	<code>double[]</code>	<code>[]</code> (empty)	Position values (joint angles or Cartesian coordinates)

Example:

```
var point = new TrajectoryPoint
{
    TimeSeconds = 0.016,
    Position = new double[] { 0.5, 1.0, 45.0, 0.0, 30.0, 10.0 }
};

Console.WriteLine($"t={point.TimeSeconds}s, pos=[{string.Join(", ",
point.Position)}]");
```

5. TrajectorySpace

Enum

Defines the coordinate space used for trajectory positions.

Name	Value	Description
Joint	0	Joint space: positions are joint angles (deg or rad)
Cartesian	1	Cartesian space: positions are tool pose (X, Y, Z, Rx, Ry, Rz)

Example:

```
// Trajectory in joint space
var jointRequest = new TrajectoryRequest { Space = TrajectorySpace.Joint };

// Trajectory in Cartesian space
var cartRequest = new TrajectoryRequest { Space = TrajectorySpace.Cartesian };
```

6. TrajectoryProfile

Enum

Defines the motion profile shape used during trajectory generation.

Name	Value	Description
Cubic	0	Cubic polynomial profile: smooth acceleration and deceleration
Trapezoidal	1	Trapezoidal velocity profile: constant acceleration phase, cruise phase, constant deceleration phase

Example:

```
// Cubic profile for smooth motion
var smoothRequest = new TrajectoryRequest
{
    Profile = TrajectoryProfile.Cubic,
    Speed = 30
};

// Trapezoidal profile with explicit acceleration
var preciseRequest = new TrajectoryRequest
{
    Profile = TrajectoryProfile.Trapezoidal,
    Speed = 50,
    Acceleration = 1000
};
```

7. CriRealtimePacketParser

Static class

Parses raw CRI data packets received from the controller into structured `CriRealTimeData` objects. Automatically converts SI units (m to mm, rad to deg) for consistent use in application code.

Constants

Constant	Type	Value	Description
PacketLength	int	308	Expected length of a CRI data packet in bytes
DefaultDecimalPlaces	int	3	Default number of decimal places for rounding

Methods

Parse

```
static CriRealTimeData Parse(byte[] packet)
```

Parses a raw CRI data packet into a `CriRealTimeData` object. Converts m to mm and rad to deg for all position and orientation values.

Parameter	Type	Description
packet	byte[]	Raw CRI data packet (must be 308 bytes)

Returns: `CriRealTimeData` -- parsed real-time data object

Example:

```
byte[] rawPacket = ReceiveCriPacket(); // your packet source
var data = CriRealtimePacketParser.Parse(rawPacket);

Console.WriteLine($"Joint Positions: [{string.Join(", ", data.JointPosition)}]");
Console.WriteLine($"TCP Pose: [{string.Join(", ", data.TcpPose)}]");
```

8. Complete CRI Control Flow Example

This example demonstrates the full CRI control workflow: starting data reception, reading the current position, generating a trajectory, sending commands via the real-time dispatcher, and cleanly shutting down.

```
using Codroid.CRI;
using Codroid.Robot;

// Initialize robot connection
var robot = new CodroidRobot("192.168.8.150");

// =====
```

```

// Step 1: Start CRI data push
// =====
// Begin receiving real-time data from the controller on the specified port
await robot.StartCriDataPush("192.168.8.150", 18888);

// =====
// Step 2: Read current position
// =====
// Use the current joint position as the trajectory start point
double[] start = robot.CriData.JointPosition;
Console.WriteLine($"Current position: [{string.Join(", ", start)}]");

// Define target position (joint angles in degrees)
double[] target = new[] { 0, 0, 90, 0, 90, 0 };
Console.WriteLine($"Target position: [{string.Join(", ", target)}]");

// =====
// Step 3: Generate trajectory
// =====
// Configure trajectory parameters
var request = new TrajectoryRequest
{
    Space = TrajectorySpace.Joint,      // Joint space
    Profile = TrajectoryProfile.Cubic,   // Smooth cubic profile
    FrequencyHz = 250,                  // 250Hz sampling
    Speed = 30                          // 30 deg/s
};

// Generate the trajectory
var trajectory = TrajectoryGenerator.Generate(start, target, request).ToList();
Console.WriteLine($"Generated {trajectory.Count} points over
{trajectory.Last().TimeSeconds:F3}s");

// =====
// Step 4: Start CRI control
// =====
// Enable real-time control mode on the controller
// filterType: 1 - Position filter type

```

```

// durationMs: 4 - Control loop period in ms
// startBuffer: 5 - Initial buffer size
await robot.StartCriControl(filterType: 1, durationMs: 4, startBuffer: 5);


try
{
    // =====
    // Step 5: Send trajectory
    // =====
    // Create a dispatcher and send the trajectory at 4ms intervals
    using var dispatcher = new CriRealtimeDispatcher("192.168.8.136");
    await dispatcher.SendTrajectory(trajectory, TrajectorySpace.Joint, periodMs: 4);

    Console.WriteLine("Trajectory execution completed");
}
finally
{
    // =====
    // Step 6: Stop CRI control
    // =====
    // Always stop CRI control and data push in finally block
    await robot.StopCriControl();
    await robot.StopCriDataPush("192.168.8.150", 18888);

    Console.WriteLine("CRI control stopped");
}

```

Workflow Diagram



Start CRI Control

|

v

Send Trajectory via Dispatcher

|

v

Stop CRI Control

|

v

Stop CRI Data Push

Important: Always stop CRI control and data push in a `finally` block to ensure clean shutdown, even if an exception occurs during trajectory execution.

7. IO and Register API Reference

IO Operations

All IO methods are on `CodroidClient` .

GetDi -- Read Digital Input

Read a digital input port. Returns `0` or `1` .

```
// Read DI port 0
int di0 = await robot.GetDi(0);
Console.WriteLine($"DI 0 = {di0}"); // 0 or 1
```

Signature:

```
Task<int> GetDi(int port)
```

Parameter	Type	Default	Description
port	int	--	Port number

Returns: `Task<int>` -- `0` or `1`

Throws: `CodroidCommandException` , `TimeoutException`

GetDo -- Read Digital Output

Read the current state of a digital output port. Returns `0` or `1` .

```
// Read DO port 10
int do10 = await robot.GetDo(10);
Console.WriteLine($"DO 10 = {do10}");
```

Signature:

```
Task<int> GetDo(int port)
```

Parameter	Type	Default	Description
port	int	--	Port number

Returns: Task<int> -- 0 or 1

Throws: CodroidCommandException , TimeoutException

GetAi -- Read Analog Input

Read an analog input port. Returns a floating-point value.

```
// Read AI port 1
double ai1 = await robot.GetAi(1);
Console.WriteLine($"AI 1 = {ai1:F3}");
```

Signature:

```
Task<double> GetAi(int port)
```

Parameter	Type	Default	Description
port	int	--	Port number

Returns: Task<double>

Throws: CodroidCommandException , TimeoutException

GetAo -- Read Analog Output

Read the current value of an analog output port.

```
// Read AO port 2
double ao2 = await robot.GetAo(2);
Console.WriteLine($"AO 2 = {ao2:F3}");
```

Signature:

```
Task<double> GetAo(int port)
```

Parameter	Type	Default	Description
port	int	--	Port number

Returns: Task<double>

Throws: CodroidCommandException , TimeoutException

SetDo -- Write Digital Output

Write a digital output. value must be 0 or 1 .

```
// Set DO port 10 to ON
await robot.SetDo(10, 1);

// Set DO port 10 to OFF
await robot.SetDo(10, 0);
```

Signature:

```
Task<CommonResponse> SetDo(int port, int value)
```

Throws ArgumentException if value is not 0 or 1 .

Parameter	Type	Default	Description
port	int	--	Port number
value	int	--	Value to write (0 or 1)

Returns: Task<CommonResponse>

Throws: CodroidCommandException , TimeoutException , ArgumentOutOfRangeException

SetAo -- Write Analog Output

Write an analog output value.

```
// Set A0 port 2 to 3.14
await robot.SetAo(2, 3.14);
```

Signature:

```
Task<CommonResponse> SetAo(int port, double value)
```

Parameter	Type	Default	Description
port	int	--	Port number
value	double	--	Analog value to write

Returns: Task<CommonResponse>

Throws: CodroidCommandException , TimeoutException

GetIoValues -- Batch Read

Batch-read multiple IO pins in a single request. Returns the raw CommonResponse whose db is a JSON array.

```
// Batch read DI0, D010, AI1, AO2
var resp = await robot.GetIoValues(new List<(string Type, int Port)>
{
    (IoPortKind.Di, 0),
    (IoPortKind.Do, 10),
    (IoPortKind.Ai, 1),
    (IoPortKind.Ao, 2),
});
Console.WriteLine(resp.db.GetRawText());

// Parse individual values
int di0 = IoGetResponseParser.ParseDigital(resp, IoPortKind.Di, 0);
double ao2 = IoGetResponseParser.ParseAnalog(resp, IoPortKind.Ao, 2);
```

Signature:

```
Task<CommonResponse> GetIoValues(IReadOnlyList<(string Type, int Port)> pins)
```

Parameter	Type	Default	Description
<code>pins</code>	<code>IReadOnlyList<(string Type, int Port)></code>	--	List of IO pins to read

Returns: `Task<CommonResponse>`

Throws: `CodroidCommandException` , `TimeoutException`

IO Helper Types

IoPortKind

Constants for the `type` field in `IOManager` protocol.

Constant	Value	Description
<code>IoPortKind.Di</code>	"DI"	Digital input
<code>IoPortKind.Do</code>	"DO"	Digital output

Constant	Value	Description
IoPortKind.Ai	"AI"	Analog input
IoPortKind.Ao	"AO"	Analog output

IoGetResponseParser

Parses the `db` field from `GetIoValues` responses.

```
// Parse a digital value
int di = IoGetResponseParser.ParseDigital(response, IoPortKind.Di, 0);

// Parse an analog value
double ai = IoGetResponseParser.ParseAnalog(response, IoPortKind.Ai, 1);

// Build a query payload
var pins = new List<(string, int)> { (IoPortKind.Di, 0), (IoPortKind.Do, 10) };
JsonElement query = IoGetResponseParser.BuildGetQuery(pins);
```

Method	Returns	Description
ParseDigital(response, ioType, port)	int	Extract 0 or 1 for DI/DO
ParseAnalog(response, ioType, port)	double	Extract floating-point value for AI/AO
BuildGetQuery(pins)	JsonElement	Build JSON array for batch IO query

Register Operations

All register methods are on `CodroidClient`.

GetRegisterValue -- Read Single Register

Read a single register. The returned `RegisterReadValue` contains the address and a raw JSON value. Use `GetInt32()` or `GetDouble()` to convert.

```
// Read register at address 49100
RegisterReadValue reg = await robot.GetRegisterValue(49100);

// Try as integer
if (reg.TryGetInt32(out int intVal))
    Console.WriteLine($"Address {reg.Address} = {intVal} (int)");
else
    Console.WriteLine($"Address {reg.Address} = {reg.GetDouble()} (float)");
```

Signature:

```
Task<RegisterReadValue> GetRegisterValue(int address)
```

Parameter	Type	Default	Description
address	int	--	Register address

Returns: Task<RegisterReadValue>

Throws: CodroidCommandException , TimeoutException

GetRegisterValues -- Batch Read

Read multiple registers in a single request. The returned list order matches the input addresses.

```
// Batch read registers 49100, 49102, 49104
var regs = await robot.GetRegisterValues(new[] { 49100, 49102, 49104 });

foreach (var r in regs)
{
    if (r.TryGetInt32(out int v))
        Console.WriteLine($" Address {r.Address}: {v}");
    else
        Console.WriteLine($" Address {r.Address}: {r.GetDouble():G}");
}
```

Signature:

```
Task<IReadOnlyList<RegisterReadValue>> GetRegisterValues(IReadOnlyList<int> addresses)
```

Parameter	Type	Default	Description
addresses	IReadOnlyList<int>	--	List of register addresses to read

Returns: Task<IReadOnlyList<RegisterReadValue>>

Throws: CodroidCommandException , TimeoutException

SetRegisterValue (int) -- Write Integer

Write an integer value to a register.

```
// Write 520 to register 49100
await robot.SetRegisterValue(49100, 520);

// Write 0 to clear
await robot.SetRegisterValue(49100, 0);
```

Signature:

```
Task<CommonResponse> SetRegisterValue(int address, int value)
```

Parameter	Type	Default	Description
address	int	--	Register address
value	int	--	Integer value to write

Returns: Task<CommonResponse>

Throws: CodroidCommandException , TimeoutException

SetRegisterValue (double) -- Write Float

Write a floating-point value to a register.

```
// Write 520.52 to register 49300
await robot.SetRegisterValue(49300, 520.52);

// Write 0.0 to clear
await robot.SetRegisterValue(49300, 0.0);
```

Signature:

```
Task<CommonResponse> SetRegisterValue(int address, double value)
```

Parameter	Type	Default	Description
address	int	--	Register address
value	double	--	Floating-point value to write

Returns: Task<CommonResponse>

Throws: CodroidCommandException , TimeoutException

SetExtendArrayType -- Set Extended Array Element Type

Set the data type of an extend-array element. Index range: 0~999.

```
// Set element 0 to Int32
await robot.SetExtendArrayType(0, RegisterExtendArrayType.Int32);

// Set element 5 to Float32
await robot.SetExtendArrayType(5, RegisterExtendArrayType.Float32);
```

Signature:

```
Task<CommonResponse> SetExtendArrayType(int index, string type)
```

Throws `ArgumentOutOfRangeException` if `index` is not in 0~999.

Throws `ArgumentException` if `type` is not a recognized value.

Parameter	Type	Default	Description
index	int	--	Extend-array element index (0~999)
type	string	--	Data type (e.g. <code>RegisterExtendArrayValueType.Int32</code>)

Returns: `Task<CommonResponse>`

Throws: `CodroidCommandException` , `TimeoutException` , `ArgumentOutOfRangeException` , `ArgumentException`

RemoveExtendArray -- Delete Extended Array Element

Remove an extend-array element and reset its data. Index range: 0~999.

```
// Remove element 0
await robot.RemoveExtendArray(0);
```

Signature:

```
Task<CommonResponse> RemoveExtendArray(int index)
```

Parameter	Type	Default	Description
index	int	--	Extend-array element index (0~999)

Returns: `Task<CommonResponse>`

Throws: `CodroidCommandException` , `TimeoutException` , `ArgumentOutOfRangeException`

RegisterReadValue Struct

Holds the result of a register read: address and raw JSON value.

Property	Type	Description
Address	int	Register address
Value	JsonElement	Raw JSON value from the controller

Method	Returns	Description
GetInt32()	int	Read as integer; throws if not convertible
GetDouble()	double	Read as floating-point
TryGetInt32(out int value)	bool	Try read as integer without throwing

```
RegisterReadValue reg = await robot.GetRegisterValue(49100);

// Safe integer read
if (reg.TryGetInt32(out int v))
    Console.WriteLine(v);

// Read as double
double d = reg.GetDouble();
```

RegisterExtendArrayValueType Constants

Supported data types for extend-array elements.

Constant	Wire Value
RegisterExtendArrayValueType.Bool	"Bool"
RegisterExtendArrayValueType.UInt8	"UInt8"
RegisterExtendArrayValueType.Int8	"Int8"
RegisterExtendArrayValueType.UInt16	"UInt16"

Constant	Wire Value
RegisterExtendArrayType.Int16	"Int16"
RegisterExtendArrayType.UInt32	"UInt32"
RegisterExtendArrayType.Int32	"Int32"
RegisterExtendArrayType.Float32	"Float32"

Full Example: IO and Register Read-Write

```
using Codroid;

ConsoleUtf8.InitConsoleUtf8();

var robot = new CodroidClient("192.168.8.136");

try
{
    await robot.ConnectRemoteAndSwitchOn();

    // --- IO ---
    // Read DI and mirror to DO
    int di0 = await robot.GetDi(0);
    Console.WriteLine($"DI 0 = {di0}");
    await robot.SetDo(10, di0);
    Console.WriteLine($"DO 10 set to {di0}");

    // Read analog values
    double ai1 = await robot.GetAi(1);
    double ao2 = await robot.GetAo(2);
    Console.WriteLine($"AI 1 = {ai1:F3}, AO 2 = {ao2:F3}");

    // Batch IO
    var batch = await robot.GetIoValues(new List<(string, int)>
    {
        (IoPortKind.Di, 0),
```

```

        (IoPortKind.Do, 10),
    });
    Console.WriteLine("Batch result: " + batch.db.GetRawText());

    // --- Register ---
    // Single read
    RegisterReadValue r = await robot.GetRegisterValue(49100);
    Console.WriteLine($"Register 49100 = {r.GetDouble():G}");

    // Batch read
    var regs = await robot.GetRegisterValues(new[] { 49100, 49102, 49104 });
    foreach (var rv in regs)
        Console.WriteLine($" {rv.Address}: {rv.GetDouble():G}");

    // Write integer
    await robot.SetRegisterValue(49100, 520);

    // Write float
    await robot.SetRegisterValue(49300, 520.52);

    // Extend array
    await robot.SetExtendArrayType(0, RegisterExtendArrayType.Int32);
    await robot.RemoveExtendArray(0);
}
finally
{
    robot.Disconnect();
}

```

8. Utilities API Reference

Publish / Subscribe (TCP Topic Push)

The controller pushes state-change notifications over TCP. Use `SubscribePublishTopic` to register a callback for a specific topic.

SubscribePublishTopic

```
Task<PublishTopicSubscription> SubscribePublishTopic(  
    string topicTy,  
    Action<PublishNotification> handler,  
    int tcMilliseconds = 100)
```

Subscribes to a TCP publish topic. The first call on a connection sends a subscription frame (no `id`). Subsequent pushes matching `topicTy` are dispatched to `handler` on the thread pool.

Parameter	Type	Default	Description
<code>topicTy</code>	<code>string</code>	--	Topic name, e.g. <code>PublishTopics.RobotStatus</code>
<code>handler</code>	<code>Action<PublishNotification></code>	--	Callback to process notifications; should not block for long
<code>tcMilliseconds</code>	<code>int</code>	100	Protocol <code>tc</code> field in milliseconds

Returns: `Task<PublishTopicSubscription>` — disposable subscription handle. Call `Dispose()` to unregister the local callback. It does NOT send an "unsubscribe" frame to the controller.

Throws: `CodroidCommandException` (controller error), `TimeoutException` (no response within 10s)

Example: Subscribe to RobotStatus

```

using Codroid;

var robot = new CodroidClient("192.168.8.136");
await robot.Connect();

// Subscribe and collect pushes for 10 seconds
int count = 0;
using var sub = await robot.SubscribePublishTopic(
    PublishTopics.RobotStatus,
    msg =>
    {
        int n = Interlocked.Increment(ref count);
        Console.WriteLine($"[{n}] ty={msg.Ty}");
        if (msg.Db.ValueKind != JsonValueKind.Undefined)
            Console.WriteLine(" db: " + msg.Db.GetRawText());
    });

await Task.Delay(TimeSpan.FromSeconds(10));
Console.WriteLine($"Received {Volatile.Read(ref count)} pushes.");
sub.Dispose(); // Stop receiving locally
robot.Disconnect();

```

PublishTopicSubscription

Disposable handle returned by `SubscribePublishTopic` . Disposing removes the local handler; the TCP connection being dropped also invalidates all subscriptions.

Member	Description
<code>TopicTy</code>	The topic name (<code>string</code>)
<code>Dispose()</code>	Unregister the local callback

PublishNotification

The notification object passed to your handler.

Property	Type	Description
Ty	string	Topic type, e.g. "publish/RobotStatus"
Db	JsonElement	Business payload; JsonValueKind.Undefined if absent
RawJson	string	Full JSON text of this message

PublishTopicsConstants

Common topic names for subscription.

Constant	Value	Description
PublishTopics.ProjectState	"publish/ProjectState"	Project run state
PublishTopics.VarUpdate	"publish/VarUpdate"	Global variable changed
PublishTopics.RobotStatus	"publish/RobotStatus"	Robot status
PublishTopics.RobotPosture	"publish/RobotPosture"	Robot posture
PublishTopics.RobotCoordinate	"publish/RobotCoordinate"	Coordinate data
PublishTopics.Log	"publish/Log"	Log messages
PublishTopics.Error	"publish/Error"	Error notifications

PublishSubscribeDefaults

Constant	Value	Description
PublishSubscribeDefaults.TcMilliseconds	100	Default tc for subscription frames

Global Variables

GetGlobalVars -- Read All

Read all global variables from the controller (raw response).

```
CommonResponse resp = await robot.GetGlobalVars();
Console.WriteLine(resp.db.GetRawText());
```

Signature:

```
Task<CommonResponse> GetGlobalVars()
```

Returns: `Task<CommonResponse>` — controller response with all global variables in `db`

Throws: `CodroidCommandException` (controller error), `TimeoutException` (no response within 10s)

GetGlobalVarsCatalog -- Read Catalog

Read all global variables and parse them into a dictionary keyed by name.

```
var catalog = await robot.GetGlobalVarsCatalog();

foreach (var kv in catalog)
{
    Console.WriteLine($"  Name: {kv.Key}");
    Console.WriteLine($"  Value: {kv.Value.Value.GetRawText()}");
    Console.WriteLine($"  Remark: {kv.Value.Remark}");
}
```

Signature:

```
Task<IReadOnlyDictionary<string, GlobalVarCatalogEntry>> GetGlobalVarsCatalog()
```

Returns: `Task<IReadOnlyDictionary<string, GlobalVarCatalogEntry>>` — dictionary keyed by variable name

Throws: `CodroidCommandException` (controller error), `TimeoutException` (no response within 10s)

SaveGlobalVar -- Save Single

Save (create or update) a single global variable.

```
// Save an integer variable
await robot.SaveGlobalVar("my_counter", 100, "test remark");

// Save a string
await robot.SaveGlobalVar("my_name", "hello_codroid");

// Save an array
await robot.SaveGlobalVar("my_arr", new[] { 1, 2, 3 });

// Save a dictionary
await robot.SaveGlobalVar("my_map", new Dictionary<string, int> { ["x"] = 10 });

// Save raw JSON literal
await robot.SaveGlobalVar("my_pose",
    new GlobalVarRawJson("{\"jp\":[1,2,3,4,5,6]}"));
```

Signature:

```
Task<CommonResponse> SaveGlobalVar(string name, object value, string? remark = null)
```

Parameter	Type	Default	Description
name	string	--	Variable name (validated by <code>GlobalVarNaming.Validate()</code>)
value	object	--	Any JSON-serializable object, or <code>GlobalVarRawJson</code>
remark	string?	null	Optional remark or description

Returns: `Task<CommonResponse>` — controller response

Throws: `CodroidCommandException` (controller error), `TimeoutException` (no response within 10s), `ArgumentException` (invalid variable name)

Variable names are validated by `GlobalVarNaming.Validate()` : must start with a letter or underscore, contain only `[A-Za-z0-9_]` , must not start with `__` , and must not collide with reserved Lua/controller identifiers.

SaveGlobalVars -- Batch Save

Save multiple global variables in one request.

```
await robot.SaveGlobalVars(new[]
{
    new GlobalVarSaveItem("sdk_test_int", 100, "integer test"),
    new GlobalVarSaveItem("sdk_test_float", 90.4, "float test"),
    new GlobalVarSaveItem("sdk_test_str", "hello", "string test"),
    new GlobalVarSaveItem("sdk_test_arr", new[] { 1, 2, 3 }),
});
```

Signature:

```
Task<CommonResponse> SaveGlobalVars(IReadOnlyCollection<GlobalVarSaveItem> items)
```

Parameter	Type	Default	Description
<code>items</code>	<code>IReadOnlyCollection<GlobalVarSaveItem></code>	--	Collection of variables to save

Returns: `Task<CommonResponse>` — controller response

Throws: `CodroidCommandException` (controller error), `TimeoutException` (no response within 10s), `ArgumentException` (invalid variable name)

RemoveGlobalVars -- Delete

Delete global variables by name. Deleting a non-existent name does not error.

```
await robot.RemoveGlobalVars(new[] { "sdk_test_int", "sdk_test_float" });
```

Signature:

```
Task<CommonResponse> RemoveGlobalVars(IEnumerable<string> names)
```

Parameter	Type	Default	Description
names	IEnumerable<string>	--	Variable names to delete

Returns: Task<CommonResponse> — controller response

Throws: CodroidCommandException (controller error), TimeoutException (no response within 10s)

Global Variable Helper Types

GlobalVarSaveItem

Record struct for saving a variable.

```
public readonly record struct GlobalVarSaveItem(  
    string Name,  
    object Value,  
    string? Remark = null);
```

Field	Description
Name	Variable name (validated)
Value	Any JSON-serializable object, or GlobalVarRawJson
Remark	Optional remark; null/blank omits the nm field

GlobalVarRawJson

Wraps a pre-formatted JSON literal to avoid double-serialization.

```
var raw = new GlobalVarRawJson("{\"jp\":[1,2,3,4,5,6]}");
await robot.SaveGlobalVar("my_pose", raw);
```

GlobalVarCatalogEntry

Parsed entry from `GetGlobalVarsCatalog` .

Property	Type	Description
Value	JsonElement	The variable's value
Remark	string	Remark string; empty if none

GlobalVarNaming

Validation utilities for global variable names.

```
// Throws ArgumentException on invalid name
GlobalVarNaming.Validate("my_var");      // OK
GlobalVarNaming.Validate("__bad");        // throws: double underscore
GlobalVarNaming.Validate("if");          // throws: reserved word

// List of reserved names
ICollection<string> reserved = GlobalVarNaming.ReservedNames;
```

Member	Description
Validate(string name)	Throws <code>ArgumentException</code> on invalid name
ReservedNames	Read-only collection of reserved identifiers

Kinematics

Forward and inverse kinematics, and relative pose calculation.

AposToCpos -- Forward Kinematics

Convert joint angles to Cartesian pose (forward kinematics).

```
var jp = new[] { 0.0, 0.0, 90.0, 0.0, 90.0, 0.0 };
var coor = new[] { 0.0, 0.0, 0.0, 0.0, 0.0, 0.0 };
var tool = new[] { 0.0, 0.0, 0.0, 0.0, 0.0, 0.0 };

// Returns parsed result directly
double[] pose = await robot.AposToCposPose(jp, coor, tool);
// pose = [x, y, z, rx, ry, rz] in mm + deg
Console.WriteLine($"TCP: [{string.Join(", ", pose)}]");

// Or get raw response
CommonResponse resp = await robot.AposToCpos(jp, coor, tool);
```

Signature:

```
Task<double[]> AposToCposPose(
    double[] jointDegrees,
    double[] userFrame,
    double[] toolFrame,
    double[]? externalAxisPositions = null)
```

Parameter	Type	Default	Description
jointDegrees	double[]	--	6 joint angles in degrees
userFrame	double[]	--	User coordinate frame [x,y,z,rx,ry,rz] (mm + deg)
toolFrame	double[]	--	Tool coordinate frame [x,y,z,rx,ry,rz] (mm + deg)
externalAxisPositions	double[]?	null	External axis positions

AposToCpos Returns: Task<CommonResponse> — controller response

AposToCposPose Returns: Task<double[]> — [x,y,z,rx,ry,rz] in mm + deg

Throws: CodroidCommandException (controller error), TimeoutException (no response within 10s)

All vectors must be exactly 6 elements. Units: degrees for joints, mm + deg for frames.

CposToApos -- Inverse Kinematics

Convert Cartesian pose to joint angles (inverse kinematics).

```
var cp = new[] { 927.503, 214.5, 898.998, 179.999, 0.0, -90.0 };
var rj = new[] { 10.0, 20.0, 30.0, 40.0, 50.0, 60.0 }; // reference joints

try
{
    double[] joints = await robot.CposToAposJoints(cp, rj);
    Console.WriteLine($"Joints (deg): [{string.Join(", ", joints)}]");
}
catch (InvalidOperationException)
{
    Console.WriteLine("No solution found. Try different reference joints.");
}
```

Signature:

```
Task<double[]> CposToAposJoints(
    double[] cartesianMmDeg,
    double[] referenceJointDegrees,
    double[]? externalAxisPositions = null)
```

Parameter	Type	Default	Description
cartesianMmDeg	double[]	--	Cartesian pose [x,y,z,rx,ry,rz] in mm + deg

Parameter	Type	Default	Description
referenceJointDegrees	double[]	--	Reference joint angles (starting guess for IK solver)
externalAxisPositions	double[]?	null	External axis positions

CposToApos Returns: Task<CommonResponse> — controller response

CposToAposJoints Returns: Task<double[]> — 6 joint angles in degrees

Throws: CodroidCommandException (controller error), TimeoutException (no response within 10s), InvalidOperationExceptionException (no IK solution found)

referenceJointDegrees is used as the starting guess. If the controller returns an empty array, an InvalidOperationExceptionException is thrown. Adjust the reference joints and retry.

CalculateRelativePose / CalculateRelativePoseResult -- Relative Pose Calculation

Calculate an offset pose relative to a tool or user coordinate frame.

```
var currentPose = new[] { 927.503, 214.5, 898.998, 179.999, 0.0, -90.0 };
var offset = new[] { 0.0, 0.0, -300.0, 0.0, 0.0, 0.0 };
```

```
// Calculate in user coordinate frame
```

```
double[] result = await robot.CalculateRelativePoseResult(
    currentPose,
    offset,
    RelativePoseCoorType.User);
```

```
Console.WriteLine($"Result: [{string.Join(", ", result)}]");
```

```
// Or use tool coordinate frame
```

```
double[] toolResult = await robot.CalculateRelativePoseResult(
    currentPose,
    offset,
    RelativePoseCoorType.Tool);
```


Signature:

```
Task<double[]> CalculateRelativePoseResult(
    double[] tcpPoseWorld,
    double[] offset,
    RelativePoseCoorType coorType,
    double[]? tcpPoseInPosCoorFrame = null,
    double[]? userCoorFrame = null)
```

Parameter	Type	Default	Description
tcpPoseWorld	double[]	--	Current TCP pose in world frame [x,y,z,rx,ry,rz]
offset	double[]	--	[dx,dy,dz,drx,dry,drz] offset
coorType	RelativePoseCoorType	--	User or Tool coordinate frame
tcpPoseInPosCoorFrame	double[]?	null	TCP pose in position coordinate frame
userCoorFrame	double[]?	null	User coordinate frame definition

CalculateRelativePose **Returns:** Task<CommonResponse> — controller response

CalculateRelativePoseResult **Returns:** Task<double[]> — [x,y,z,rx,ry,rz] relative pose in mm + deg

Throws: CodroidCommandException (controller error), TimeoutException (no response within 10s)

RelativePoseCoorType

Value	Integer	Description
RelativePoseCoorType.User	0	User coordinate frame
RelativePoseCoorType.Tool	1	Tool coordinate frame

ConsoleUtf8

Sets `Console.InputEncoding` and `Console.OutputEncoding` to UTF-8. On Windows this prevents Chinese character garbling. On Linux/macOS it is a no-op.

Signature:

```
public static void InitConsoleUtf8()
```

Example:

```
using Codroid;

// Call at program entry
ConsoleUtf8.InitConsoleUtf8();

var robot = new CodroidClient("192.168.8.136");
// ... rest of your program
```

Full Example: Utilities

```
using System;
using System.Text.Json;
using System.Threading;
using Codroid;

ConsoleUtf8.InitConsoleUtf8();

var robot = new CodroidClient("192.168.8.136");

try
{
    await robot.ConnectRemoteAndSwitchOn();

    // --- Publish/Subscribe ---
    using var sub = await robot.SubscribePublishTopic(
```

```

        PublishTopics.RobotStatus,
        msg => Console.WriteLine($"Push: ty={msg.Ty}"));

// --- Global Variables ---
await robot.SaveGlobalVar("sdk_demo", 42, "demo variable");
var catalog = await robot.GetGlobalVarsCatalog();
if (catalog.TryGetValue("sdk_demo", out var entry))
    Console.WriteLine($"sdk_demo = {entry.Value.GetRawText()}");

await robot.RemoveGlobalVars(new[] { "sdk_demo" });

// --- Kinematics ---
var jp = new[] { 0.0, 0.0, 90.0, 0.0, 90.0, 0.0 };
var zero = new[] { 0.0, 0.0, 0.0, 0.0, 0.0, 0.0 };

double[] tcp = await robot.AposToCposPose(jp, zero, zero);
Console.WriteLine($"FK result: [{string.Join(", ", tcp)}]");

try
{
    double[] joints = await robot.CposToAposJoints(tcp, jp);
    Console.WriteLine($"IK result: [{string.Join(", ", joints)}]");
}
catch (InvalidOperationException)
{
    Console.WriteLine("IK: no solution with given reference.");
}

double[] offsetResult = await robot.CalculateRelativePoseResult(
    tcp, new[] { 0, 0, -100, 0, 0, 0 }, RelativePoseCoorType.Tool);
Console.WriteLine($"Relative pose: [{string.Join(", ", offsetResult)}]");

sub.Dispose();
}
finally
{
    robot.Disconnect();
}

```


9. .NET Framework 4.6.2 Notes

This section covers the platform constraints, timing behavior, polyfill layer, and build considerations when using the Codroid SDK on .NET Framework 4.6.2.

1. Platform Constraint

.NET Framework 4.6.2 runs only on **Windows**. Linux and macOS are not supported.

```
<!-- Only valid on Windows -->
<TargetFramework>net462</TargetFramework>
```

2. Target Framework

The SDK uses multi-targeting. The `net462` target is built alongside `net6.0` and `net8.0`.

```
<!-- From CodroidCS.csproj -->
<TargetFrameworks>net462;net6.0;net8.0</TargetFrameworks>
```

Your test project should reference the SDK and target `net462` :

```
<PropertyGroup>
  <OutputType>Exe</OutputType>
  <TargetFramework>net462</TargetFramework>
  <LangVersion>10</LangVersion>
</PropertyGroup>

<ItemGroup>
  <ProjectReference Include="..\CodroidSDK\CodroidCS.csproj" />
</ItemGroup>
```

3. CRI 250Hz SLA

The default and supported CRI real-time control frequency is **250Hz** (`periodMs = 4`).

- `periodMs = 4` is the **default SLA** -- tested and supported out of the box.
- `periodMs != 4` (including 500Hz / 1000Hz) is **NOT** within the default SLA. Higher frequencies require **on-site validation** of jitter and controller behavior.

When `periodMs != 4` , the SDK logs a warning via `Trace.TraceWarning` :

```
[Codroidsdk][net462] CRI SendTrajectory periodMs=N is outside the default 250Hz SLA.
The default supported period is 4ms. Higher-frequency or custom-period control
requires on-site validation.
```

4. Timing Implementation

On .NET 6+, `SendTrajectory` uses `PeriodicTimer` . On `net462`, `PeriodicTimer` is unavailable. The SDK falls back to:

1. **Stopwatch** -- high-resolution elapsed time measurement.
2. `Thread.Sleep(1)` -- for remaining time > 1.5ms (yields CPU).
3. `Thread.SpinWait(50)` -- for remaining time <= 1.5ms (busy-wait for precision).

```
// Simplified net462 timing loop
long ticksPerPeriod = (long)(Stopwatch.Frequency * periodMs / 1000.0);
long nextTick = stopwatch.ElapsedTicks;

foreach (var point in trajectory)
{
    await SendCommand(point.Position, space, ct);
    nextTick += ticksPerPeriod;
    long remainingTicks = nextTick - stopwatch.ElapsedTicks;

    if (remainingTicks > 0)
    {
```

```
double remainingMs = remainingTicks * 1000.0 / Stopwatch.Frequency;
if (remainingMs > 1.5)
    Thread.Sleep(1);    // coarse wait
else
    Thread.SpinWait(50); // fine wait
}
```

5. Jitter Statistics

After `SendTrajectory` completes on net462, the SDK outputs jitter statistics via `Trace.TraceInformation`.

```
[Codroidsdk][net462] CRI SendTrajectory statistics:
Duration: 4.12s
Frames sent: 1031
Average period: 4.005ms
Max period: 5.823ms
Overruns (>6ms): 0
Max consecutive overruns: 0
UDP exceptions: 0
```

Metric	Description
Duration	Total elapsed time
Frames sent	Number of UDP frames sent
Average period	Mean inter-frame interval
Max period	Worst-case inter-frame interval
Overruns (>6ms)	Frames exceeding 6ms interval
Max consecutive overruns	Longest streak of consecutive overruns
UDP exceptions	Socket errors during send

6. TraceWarning for periodMs != 4

If you call `SendTrajectory` with any `periodMs` value other than 4, the SDK emits a `Trace.TraceWarning` before starting. This is informational only -- execution proceeds normally.

7. Polyfill Layer

Five polyfill files provide missing .NET 6+ APIs when targeting net462. All are in `CodroidSDK/Compat/`.

7.1 `ArgumentNullException.ThrowIfNull`

File: `Polyfills.cs`

On net462, `ArgumentNullException.ThrowIfNull` does not exist. The SDK provides `Polyfills.ThrowIfNull` with `CallerArgumentExpression` for automatic parameter name capture.

```
// Internal usage
Polyfills.ThrowIfNull(argument); // auto-captures param name

// On net6+ this delegates to ArgumentNullException.ThrowIfNull
```

7.2 `Math.Clamp`

File: `MathPolyfills.cs`

`Math.Clamp` is not available in .NET Framework. The SDK provides `MathPolyfills.Clamp` with identical semantics.

```
// int overload
int clamped = MathPolyfills.Clamp(value, min, max);

// double overload
double clampedD = MathPolyfills.Clamp(value, 0.0, 1.0);
```


7.3 double.IsFinite

File: DoublePolyfills.cs

`double.IsFinite` is not available in .NET Framework. The SDK provides `DoublePolyfills.IsFinite`.

```
bool ok = DoublePolyfills.IsFinite(d); // true if not NaN and not Infinity
```

7.4 IsExternalInit

File: IsExternalInit.cs

The `init` accessor keyword requires `System.Runtime.CompilerServices.IsExternalInit`, which does not exist in net462. This polyfill adds the marker type.

```
// Enables C# init properties on net462
public string Name { get; init; } = "";
```

7.5 CallerArgumentExpressionAttribute

File: CallerArgumentExpressionAttribute.cs

The `[CallerArgumentExpression]` attribute is a C# 10 / .NET 6+ feature. This polyfill declares the attribute for net462, enabling `Polyfills.ThrowIfNull` to capture parameter names automatically.

8. NuGet Dependencies

When targeting net462, the SDK pulls in two additional NuGet packages:

Package	Version	Purpose
<code>System.Text.Json</code>	8.0.5	JSON serialization
<code>System.Memory</code>	4.5.5	<code>Span<T></code> , <code>Memory<T></code> support

```
<!-- From CodroidCS.csproj -->
<ItemGroup Condition="'$(TargetFramework)' == 'net462'">
  <PackageReference Include="System.Text.Json" Version="8.0.5" />
  <PackageReference Include="System.Memory" Version="4.5.5" />
</ItemGroup>
```

9. UdpClient Differences

The `UdpClient` API differs between .NET Framework and .NET 6+. The SDK uses conditional compilation to handle this.

SendAsync

On net462, `UdpClient.SendAsync` is not available with `ReadOnlyMemory<byte>`. The SDK uses the synchronous `Send` method instead.

```
#if NET462
    _udp.Send(buffer, length, target);           // synchronous
    await Task.CompletedTask;
#else
    await _udp.SendAsync(buffer.AsMemory(), target, ct); // async
#endif
```

ReceiveAsync with Cancellation token

On net462, `ReceiveAsync(CancellationToken)` is not available. The SDK registers a cancellation callback that closes the socket, causing the blocking `ReceiveAsync()` to throw.

```

#if NET462
    using var reg = token.Register(() =>
    {
        try { _udpClient?.Close(); } catch { }
    });
    // Then: await _udpClient.ReceiveAsync() (no token)
#else
    await _udpClient.ReceiveAsync(token);
#endif

```

WriteDoubleLittleEndian

On net462, `BinaryPrimitives.WriteDoubleLittleEndian(Span<byte>, double)` is not available. The SDK falls back to `BitConverter.GetBytes` with manual endianness handling.

```

#if NET462
    byte[] bytes = BitConverter.GetBytes(value);
    if (!BitConverter.IsLittleEndian) Array.Reverse(bytes);
    Array.Copy(bytes, 0, buffer, offset, 8);
#else
    BinaryPrimitives.WriteDoubleLittleEndian(buffer.AsSpan(offset, 8), value);
#endif

```

10. LangVersion = 10

Both the SDK and net462 test projects set `<LangVersion>10</LangVersion>`. This enables C# 10 features (file-scoped namespaces, `init`, global usings, etc.) even on net462.

```

<PropertyGroup>
  <TargetFramework>net462</TargetFramework>
  <LangVersion>10</LangVersion>
  <ImplicitUsings>enable</ImplicitUsings>
  <Nullable>enable</Nullable>
</PropertyGroup>

```

11. Running the net462 Test Projects

BasicAPI Test

```
# Full suite (IO, register, kinematics, publish, global vars)
dotnet run --project CodroidTestNet462/CodroidTestNet462.csproj -- 192.168.8.10

# Single IO test
dotnet run --project CodroidTestNet462/CodroidTestNet462.csproj -- io 192.168.8.10

# Single register test
dotnet run --project CodroidTestNet462/CodroidTestNet462.csproj -- register
192.168.8.10
```

CRI Real-Time Control Test

```
# All segments (joint + cartesian + path)
dotnet run --project CodroidCRITestNet462/CodroidCRITestNet462.csproj

# Joint only
dotnet run --project CodroidCRITestNet462/CodroidCRITestNet462.csproj -- joint

# Cartesian with custom speed
dotnet run --project CodroidCRITestNet462/CodroidCRITestNet462.csproj -- cart --speed
120 --accel 600

# Path with specific IPs
dotnet run --project CodroidCRITestNet462/CodroidCRITestNet462.csproj -- path
192.168.8.10 192.168.8.150

# Duration mode (6 seconds)
dotnet run --project CodroidCRITestNet462/CodroidCRITestNet462.csproj -- cart --
duration 6
```

Summary of net462 vs net6.0+ Differences

Aspect	net462	net6.0+
Platform	Windows only	Windows, Linux, macOS
CRI timer	<code>Stopwatch</code> + <code>Thread.Sleep(1)</code> + <code>SpinWait(50)</code>	<code>PeriodicTimer</code>
UDP send	<code>UdpClient.Send</code> (sync)	<code>UdpClient.SendAsync</code> (async)
UDP receive cancellation	<code>token.Register(Close)</code>	<code>ReceiveAsync(token)</code>
Double write	<code>BitConverter.GetBytes</code> + manual endian	<code>BinaryPrimitives.WriteDoubleLittleEndian</code>
<code>Math.Clamp</code>	<code>MathPolyfills.Clamp</code>	<code>Math.Clamp</code>
<code>double.IsFinite</code>	<code>DoublePolyfills.IsFinite</code>	<code>double.IsFinite</code>
init accessor	Polyfill (<code>IsExternalInit.cs</code>)	Built-in
<code>[CallerArgumentExpression]</code>	Polyfill	Built-in
NuGet extras	<code>System.Text.Json</code> 8.0.5 , <code>System.Memory</code> 4.5.5	None